



VOSS



**VOSS Insights
Arbitrator Administration Guide**

Release 23.3

Dec 13, 2023

Legal Information

- Copyright © 2023 VisionOSS Limited.
All rights reserved.
- This information is confidential. If received in error, it must be returned to VisionOSS ("VOSS"). Copyright in all documents originated by VOSS rests in VOSS. No portion may be reproduced by any process without prior written permission. VOSS does not guarantee that this document is technically correct or complete. VOSS accepts no liability for any loss (however caused) sustained as a result of any error or omission in the document.

DOCUMENT ID: 20231213173354

Contents

- 1 What's New** **1**
 - 1.1 Arbitrator Administration Guide: Release 23.3 1

- 2 Getting Started** **3**
 - 2.1 Introduction 3
 - 2.2 Arbitrator Licensing 3
 - 2.3 License Auditing 5

- 3 Correlate** **9**
 - 3.1 Correlate 9

- 4 Configuration** **33**
 - 4.1 Introduction to Arbitrator System Configuration 33
 - 4.2 Policy Configuration 34
 - 4.3 Asset Configuration 50
 - 4.4 Probe Configuration 61
 - 4.5 Controls 70
 - 4.6 Response Procedure Configuration 72
 - 4.7 Credential Configuration 79
 - 4.8 Customer Configuration 80
 - 4.9 Access Control 83
 - 4.10 Import & Export 97
 - 4.11 Archive Management 99
 - 4.12 Tools 129

- 5 Arbitrator Maintenance** **133**
 - 5.1 Backup and Restore the Arbitrator 133
 - 5.2 System Recovery 136
 - 5.3 Network Observability 137

1. What's New

1.1. Arbitrator Administration Guide: Release 23.3

- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Introduction to Arbitrator System Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Policy Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Asset Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Probe Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Controls](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Response Procedure Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Credential Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Customer Configuration](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Access Control](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Import & Export](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Archive Management](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.
- EKB-17216: SAML: Dashboard sign out redirects to auto sign-in. See: [Tools](#)
Added a note for SAML configuration that the Sign Out option will not display when SAML is enabled.

- EKB-18103: Pull BOT testing scripts into Arbitrator - phase 2. See: [Archive Management](#)
Added details around the DEM agent added to the Arbitrator for testing connectivity to web-based systems.
- EKB-18181: Allow control of periodic file processing via the user interface. See: [Archive Management](#)
Added details for the Control to enable and disable cron jobs for file processing.
- VOSS-1213: Implement VOSS Insights License Audit Capabilities. See: [License Auditing](#)
Added details around generating a license file.
- VOSS-1213: Implement VOSS Insights License Audit Capabilities. See: [Archive Management](#)
Added details around generating a license file.

2. Getting Started

2.1. Introduction

Welcome to Insights Arbitrator, a powerful log analytics platform that allows multiple data sources and log formats to be consumed, extracted, analyzed, and correlated, for complete event, alarm and systems monitoring.

This guide describes how to use and administer the Arbitrator platform. You can use this guide for help with importing assets, importing scripts, configuring new correlation rules, searching logs, assigning scripts to assets to create probes, and for overall performance management of the systems monitored.

Note: This guide is aimed at system administrators and users responsible for configuring and monitoring the Correlation platform. Users should have a working knowledge of operating systems, software applications, and network elements.

The Arbitrator platform design allows it to be used in multiple workflows. While you won't need to follow any particular linear flow, some elements must be configured in a specific order. Those will be pointed out in each section.

This guide covers the following:

- Correlate - the main user interface, which allows you to visualize the monitored systems and to manage alerts for these systems. The views within this workspace are constantly updating with newly gathered data.
- Configuration - this is the workspace used to install and set up the platform.

2.2. Arbitrator Licensing

2.2.1. Overview

You can view the Arbitrator License remaining days in the user interface, once you log in.


This setting can be enabled (display) or disabled (hide).



2.2.2. Show or Hide Days Remaining from the UI

You can choose to show or hide the license days remaining from the main user interface. To do this:

1. In **ACCESS CONTROL**, select **Permission Groups**.
2. Toggle the following setting: **VIEW - License Expiration**



2.2.3. View License Days Remaining

To see how many days left, from the main menu, for a logged in user:

1. Choose **About**
2. Check the **DAYS LICENSED** and **DAYS REMAINING** values.

2.2.4. Load a License File

To load a license file:

1. Obtain the license file
2. Choose **About**
3. Click **EDIT PRODUCT KEY** and replace it with the one from the license file.

Note: When updating a license file, any custom theme that is applied remains active.

2.3. License Auditing


2.3.1. Overview

VOSS Insights integrates with the VOSS Cloud Licensing service to provide license auditing capabilities that allows you to view and inform VOSS of your license usage counts across various services and devices, including Cisco Unified Communications Manager (CUCM), Webex, Zoom, and Microsoft Teams.

A backend service on the Arbitrator detects probes already configured for CUCM, UCCE, UNITY, Webex, and MS Teams devices, and automatically retrieves the user accounts for the respective services.

Insights ships with resource files for the following views, which allow you to create dashboards that display user license counts for your system:

- data_user_view
- standalone_count_view
- meeting_room_count_view



The license auditing service generates a file that can be automatically sent to the VOSS Cloud Licensing service for processing.

Note: If you prefer to opt out of the automated license delivery mechanism, you will need to manually upload the license user count details to VOSS.

Related Topics

- [License Tab](#)

2.3.2. Register with the VOSS Cloud Licensing Service and Upload License File

This procedure registers your organization for syncing with the VOSS Cloud Licensing service, and optionally, allows for the license file to be automatically uploaded to the VOSS Customer Portal. Alternatively, once you've registered, you can manually upload the license file.

Registering allows licensed user counts to be added to a file that is generated on Insights Arbitrator. These files are generated daily.

Before you start

- Open the following ports to communicate with the VOSS Customer Portal at *voss.portalshape.com/*
 - Default HTTP: port 80
 - Default HTTPS: port 443
- Add the host name to an allowlist for trusted servers: *platform.voss-solutions.com*

Note: If your system is unable to reach external sites on the internet, you can use a proxy server that you set up on the Arbitrator (via **Configuration > Archive Management > Configuration Management > Proxy tab**)

Register and upload license file

1. Log in to Arbitrator as administrator, then click the toolbar **Wrench** icon (System Configuration) to open the **Configuration** GUI.
2. Click **Archive Management**, then on the **Archive Management** page, select the **License** tab.
3. Fill out your organization ID, your environment type (for example, staging, trial, or lab), and optionally, a device description.

Note: You can obtain your organization ID from the VOSS Customer Portal. Registration and file upload fails if the organization ID is incorrect.


4. To allow automatic upload of generated license file to the VOSS Customer Portal, set the value of the **enabled** drop-down to **true**.

Note: If you wish to opt out of automatic file uploads, set the value to `false` (default).

5. Click **Save** to generate the license file for the organization ID you provided.
6. (Optional) On the **License** tab, click **Fetch License File**.

Note: Clicking **Fetch License File** before saving triggers an error as the license file won't have been generated yet.

To view the content of the license file you can click **View Output**.



Alternative steps:

- Option 1 - Copy license file details, and submit the details to VOSS:
 - On the **License** tab, click **Fetch License File**.
 - Click **View Output** to display the contents of the license file in a dialog on this page.
 - Copy the license file contents, and submit the details to VOSS.
- Option 2 - Download the file, and submit it to VOSS:
 - Copy the last part of the path that appears below the **Fetch License File** button (`license/latest.csv`)
 - Append the copied text to your system IP address in a URL (in a new tab).
 - The license file downloads as a `.csv` file.
 - Upload the file to the VOSS Customer Portal.

Related Topics

- [Archive Management \(Proxy\) in the VOSS Insights Arbitrator Administration Guide.](#)

3. Correlate

3.1. Correlate

3.1.1. Menu Bar

There are distinct functional 'Views' within the interface. Each will be covered in its own section of this guide.

- Policy Monitor
- Asset Explorer
- Alarm Analyzer
- Event Search
- Call Path Monitor
- Call Detail Monitor

This menu is located at the top of the browser page and allows you to navigate to each of the Arbitrator views. Each are shown below:



1. 2. 3. 4. 5. 6. 7. 8. 9. 10. 11. 12.


1. Policy Configuration
2. Asset Configuration
3. Probe Configuration
4. Controls
5. Response Procedures
6. Credentials
7. Customers
8. Access Control
9. Import / Export
10. Archive Management
11. Tools
12. Admin

3.1.2. Assets

Asset Overview

Each Asset is colored to reflect its current Alert Status. The status colors available and their meanings are below:

- Red (Critical)
- Orange (Major)
- Yellow (Minor)
- Blue (Informational / Notification)
- Green (Healthy)



You can click on any of the assets to display the summarized alarm statistics for that asset. A box will open in the upper right corner of the screen to show the details. To see greater detail about the status of the asset, click on the underlined [View Asset Details](#) in the bottom of the box. This will take you to the Asset Details view. (See Asset Details view under the Asset Explorer Section)

Asset Explorer

Asset Explorer gives a view into the current alarm state of the assets monitored by Arbitrator.


Only devices created as Assets in the Arbitrator system will be rendered in the view. Since Correlated events create alarms in the system, asset icon colors will change to reflect the severity level of the alert. Assets display the color of the current highest-level alert for that asset in the system.

Alert Severity Levels:

- Red (Critical)
- Orange (Major)
- Yellow (Minor)
- Blue (Informational / Notification)
- Green (Healthy)




Asset Filtering



The Assets displayed can be filtered using the filtering pane on the left. This includes:

- Filtering by Alert Severity levels, including **Maintenance Mode**.
- Asset Type
- Defined Asset Groups
- Keyword

Asset Explorer Navigation



The Asset Explorer will display up to 100 assets per page. Use the navigation button in the top right to grab the next 100 assets or the specific increment you have set.

Asset Details View

The Asset Details View is opened when you double click on any of the assets in the Asset Explorer view. Once open the view contains 3 tabs:

- Alerts
- Probes
- Search

Click Close in the upper right corner of the screen to return to the Asset Explorer view.

Asset Details: Alerts Tab

The screenshot displays the 'ASSET DETAILS' window for IP 10.13.37.43. The 'ALERTS' tab is active, showing a table of alerts. The first alert is a 'Major Cisco Error' with a status of 'OPEN'. Below the table, there are sections for 'DETAILS' and 'DESCRIPTION'. The 'DETAILS' section shows metadata for the selected alert, including 'REFERENCE ID', 'NODE', 'POLICY', 'RULE', 'OWNER', and 'STATUS'. The 'DESCRIPTION' section shows a list of alert entries with their respective dates, times, and outputs.

DATE	NODE	POLICY	RULE	STATUS	OWNER
07/08/18 11:57:06 AM	deparb	Cisco Alerts : Universal	Critical Cisco Error	OPEN	Unassigned
07/08/18 09:25:15 AM	deparb	Cisco Alerts : Universal	Major Cisco Error	OPEN	Unassigned
07/08/18 09:18:21 AM	deparb	Cisco Alerts : Universal	Critical Cisco Error	OPEN	Unassigned

This tab displays all alerts associated with the asset and allows the user to disposition, add alert journal entries for the alert and see a report of the alert and events. (See Alert Disposition, Alert Journal and View Report within the Alert Analyzer Section)

Asset Details: Probes

ASSET DETAILS • 10.13.37.43

TYPE Unknown
IP 10.13.37.43
ALIAS Unknown
MAC Unknown

HOSTNAME 10.13.37.43
TIMEZONE Unknown
VENDOR Unknown
MODEL Unknown

VERSION Unknown
DESCRIPTION

ALERTS **PROBES**

Trunk Activity
Call Manager RTMT Request
Call Activity
Call Manager Service
Gateway Activity
CPU and Memory

CPU and Memory

RAW DETAILS

```

Get rate this took 0.061254 seconds to send a request to https://10.13.37.43/ast/ASTraop.d?GetPreCarvedIntoItems-getCpuAndMemoryRequest
Status: 200
<?xml version="1.0"?><PreCarvedResponse ReturnCode="0" CollectingRate="30" AMC="CUCM12" RxCID="CUCM12"><getCpuAndMemoryReply ReturnCode="0" ErrorMessage=""
Timestamp="153107141" NumOfProcessors="1"><Host Name="CUCM12" ReturnCode="0" ErrorMessage=""><Memory UsedKbytes="519368" FreeKbytes="118454" TotalKbytes="1028812"
SharedKbytes="62396" BufferKbytes="309680" CachedKbytes="451868" TotalSwapKbytes="4066496" UsedSwapKbytes="118552" FreeSwapKbytes="3977944" VmPercentageUsed="37"
MemPercentageUsed="51"?><Processor Name="0" PercentageUser="3" PercentageNice="0" PercentageSystem="4" PercentageIdle="91" PercentageIoq="0" PercentageIoqTrp="0"
PercentageOWeb="1" PercentageCPU="8"?><Processor Name="3" PercentageUser="3" PercentageNice="0" PercentageSystem="3" PercentageIdle="90" PercentageIoq="0"
PercentageIoqTrp="0" PercentageOWeb="4" PercentageCPU="11"?><Processor Name="4" PercentageUser="0" PercentageNice="0" PercentageSystem="1" PercentageIdle="99"
PercentageIoq="0" PercentageIoqTrp="0" PercentageOWeb="0" PercentageCPU="11"?><Processor Name="3" PercentageUser="0" PercentageNice="0" PercentageSystem="1"
PercentageIdle="99" PercentageIoq="0" PercentageIoqTrp="0" PercentageOWeb="0" PercentageCPU="13"?><Processor Name="2" PercentageUser="0" PercentageNice="0"
PercentageSystem="1" PercentageIdle="98" PercentageIoq="0" PercentageIoqTrp="0" PercentageOWeb="0" PercentageCPU="4"?><Processor Name="1" PercentageUser="2"
  
```

RANGE: 1 HOUR

Displaying 1 - 24 of 24

This tab displays all probes associated with the asset. Clicking on each probe will display the probes output. If output is a numerical value, such as CPU usage, then a graph will be displayed of that value over time. If the probe output is non-numerical then just the last probe output will be displayed.

Asset Details: Search

This tab contains an event search bar tied to the data only associated with this asset. This allows the user to search all logs / events by this particular asset versus the entire index data store. (See Event Search for more details)

ASSET DETAILS • 10.13.37.43

TYPE Unknown
IP 10.13.37.43
ALIAS Unknown
MAC Unknown

HOSTNAME 10.13.37.43
TIMEZONE Unknown
VENDOR Unknown
MODEL Unknown

VERSION Unknown
DESCRIPTION

ALERTS **PROBES** **SEARCH**

1 Last 24 Hours

Displaying 1 - 10 of 221,614 events • first prev next last • 10

```

1
07/08/18
11:53:22 AM
<packageContext id="1" name="callData">
  <timestamp key="2018-07-08 10:51:21">
    <sessionId key="a9d40644b8b6e-3481-e811-80d4-031040def81a">
      <registrarIP key="10.13.37.44">
        <translatIP key="">
          <registrarDomain key="">
            <source key="1028172.16.1.11">
              <destination key="4098">
                <letCallIdReason key="EndedBySecurityDenial">
                  <reason key="Layack">
                    <comments>
                      <latcbema corderId="callResponseCodes" version="1.2" method="">
                        <sessionOutput>
                          <PDU code="195" message="Trying received" local="172.16.1.11" remote="10.13.37.44"/>
                          <PDU code="481" message="Unauthorized received" local="172.16.1.11" remote="10.13.37.44"/>
                          <PDU code="195" message="Trying received" local="172.16.1.11" remote="10.13.37.44"/>
                          <PDU code="200" message="OK received" local="172.16.1.11" remote="10.13.37.44"/>
                          <PDU code="481" message="Call Leg/Transaction Does Not Exist (329 bytes) to" local="172.16.1.11" remote="10.13.37.44"/>
                          <PDU code="195" message="Trying received" local="172.16.1.11" remote="10.13.37.43"/>
                          <PDU code="481" message="Forbidden received" local="172.16.1.11" remote="10.13.37.43"/>
                        </sessionOutput>
                      </latcbema>
                    </comments>
                  </packageContext>
                <letCallError=><message>Could not find call_metrics_wml key tag</message></letCallError>
              
```

Host: 172.16.1.11 Port: 10.13.37.110:64005 Method: xml_message.xml

```

2
<!--241 8 2018 16:51:40 10.13.37.7: 494 <190> 2018-07-08T11:51:39-05:00 PA-500.layacktech.com - - - 1,2018/07/08 11:51:38,029401023698,TRAFFIC, end,2049,2018/07/08
11:51:38,10.13.37.43,216.239.35.12,71.41.183.98,216.239.35.12,Dev-External,,ntp,vyssi,Dev-Trust,External-Untrust,ethernet1/2,ethernet1/1,Demo,2018/07/08
11:51:38,33729,1,35549,123,51835,123,8a402653,udp,allow,630,360,270,7,2018/07/08 11:51:08,1,any,0,2207257887,8x0,10.0.0.0-10.255.255.255,United States,0,4,3,aged-
out,0,0,0,0,PA-500,From-policy,,0,,0,,N/A,0,0,0,0
Host: 10.13.37.7 Port: 10.13.37.110:514 Method: tcp_spylog
3
<!--241 8 2018 16:51:40 10.13.37.7: 493 <190> 2018-07-08T11:51:38-05:00 PA-500.layacktech.com - - - 1,2018/07/08 11:51:37,029401023698,TRAFFIC, end,2049,2018/07/08
11:51:37,10.13.37.43,216.239.35.12,71.41.183.98,216.239.35.12,Dev-External,,ntp,vyssi,Dev-Trust,External-Untrust,ethernet1/2,ethernet1/1,Demo,2018/07/08
11:51:37,38737,1,42132,123,45559,123,0a402653,udp,allow,630,360,270,7,2018/07/08 11:51:08,2,any,0,2207257887,8x0,10.0.0.0-10.255.255.255,United States,0,4,3,aged-
out,0,0,0,0,PA-500,From-policy,,0,,0,,N/A,0,0,0,0
Host: 10.13.37.7 Port: 10.13.37.110:514 Method: tcp_spylog
  
```

3.1.3. Alerts

Alert Analyzer

The Alert Analyzer screen displays all of the alerts coming into the system based on a first in / last out presentation. It allows the user to see the alerts as they are happening or ones that have been in existence for a period of time. It also provides the ability to disposition the alerts based on activity as well as view a report with specific details associated with the alert. There are also several filter and sort options available to apply to the view.

The screenshot shows the Alert Analyzer interface. At the top, it displays 'ALERT ANALYZER' and 'Displaying 1 - 10 of 3,702 Alerts'. Below this are controls for 'FILTERS', 'SORT', 'BULK DISPOSITION', and 'STATUS'. The main area contains a table of alerts with columns for DATE, NODE, POLICY, RULE, STATUS, and OWNER. One alert is expanded to show details, including a 'REFERENCE ID', 'NODE', 'POLICY', 'RULE', 'OWNER', 'STATUS', 'START', 'LAST CHANGE', 'ELAPSED TIME', 'NEXT ESCALATION', 'EXPIRES IN', and 'RESPONSE PROCEDURE'. The expanded alert details show a 'Critical Cisco Error' with a message about 'Attempting Control Method (LinkToAlert) Parameters'. Below the details is a 'DESCRIPTION' section with a table of related alerts.


DATE	NODE	POLICY	RULE	STATUS	OWNER
07/07/18 01:01:17 PM					
07/07/18 01:01:29 PM	devpart	Catch all test	Catch all test	OPEN	Unassigned
07/07/18 01:01:38 PM	devpart	Cisco HCS PCA	RTMT_ALERT	OPEN	Unassigned
07/07/18 01:02:21 PM	devpart	Cisco Alerts : Universal	Critical Cisco Error	OPEN	Unassigned
07/07/18 01:02:38 PM	devpart	Cisco HCS PCA	RTMT_ALERT	OPEN	Unassigned
07/07/18 01:02:40 PM	devpart	Catch all test	Catch all test	OPEN	Unassigned

Alert Disposition

The drop-down box allows you to set the status of each alert. The can be set one at a time or by bulk. The available options are:

- Open: This is a new alert.
- Under Review: Moved out of the open state and the alert journal can still be edited.
- Acknowledge: Moved out of the open state and the alert journal can still be edited.
- Release: Moved out of the open state and the alert journal can still be edited.
- Close: Moved out of the open state and the alert journal can still be edited.
- Disregard: The alert is deleted from the system.
- Close and Locked: Moved to a closed state and the alert journal cannot be edited.


To disposition an alert simply open the alert by expanding it (click the up and down arrows to the far right of the alert). Once open select the drop-down box next to "Status" and select the disposition state.



Bulk Disposition: This will allow the user to disposition a group of alerts at once. First apply the required filter to the alerts by using the Filter Manager (See Alert Filters). Once you have the group of alerts filtered then select the desired disposition state from the “Bulk Disposition” drop-down box.

Filtering by Disposition

By clicking the drop-down box “Status” you can choose to see only the alerts with a specific disposition status. Once open select your choice(s) by checking the boxes and click update. The screen will show only the ones you have selected.



Alert Filters

Alert Filters provide the ability to filter all of the alerts by Keywords, Severity and Date & Time. Open the “Filter Manager” by selecting the wrench icon in the top left of the screen next to the word Filters. Click the “Add” button to add a new filter.

- Keywords: Fill in the detail to filter by. Choose to enter one, many or all of the criteria fields.
 - Name: Sets the name of the filter for your reference
 - Description: Description of the filter
 - Policy: Filter by the name of the correlation policy
 - Rule: Filter by the name of the correlation rule
 - Group: Filter by the name of the group
 - Customer: Filter by the name of the customer
 - Site: Filter by the site
 - Node: Filter by the node
 - Message: Filter by the message
 - Owner: Filter by the owner

The screenshot shows the 'FILTER MANAGER' window. At the top right are 'SAVE' and 'CANCEL' buttons. Below the title bar are '+ ADD' and '- REMOVE' buttons. The main area is divided into two sections. On the left, there is a list of filters; one filter named 'Test' is selected, with a description 'This is a test filter' and 'ALLOW' and 'DISREGARD' buttons. On the right, there is a form for configuring a filter. The form has tabs for 'KEYWORDS', 'SEVERITY', and 'DATE & TIME'. The 'KEYWORDS' tab is active, showing fields for NAME (Test), DESCRIPTION (This is a test filter), POLICY, RULE (Critical Cisco Error), GROUP, CUSTOMER, SITE, NODE, MESSAGE, and OWNER.

- Severity: The filter can be set based on the chosen severity or severities. Additionally, the state or states can be chosen with each severity. Click the levels desired.
 - Active: Alert is currently in one of the active states
 - Escalated: Alert has been escalated based on the timer in the correlation rule
 - Acknowledged: Alert is in an acknowledged disposition state.
 - Expired: Alert has expired based on the timer set in the correlation rule

SEVERITY	ACTIVE	ESCALATED	ACKNOWLEDGED	EXPIRED
CRITICAL	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
MAJOR	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
MINOR	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
INFORMATIONAL	<input checked="" type="checkbox"/>			

- Date & Time: The filter can be set based on a date range, by “All Day”, by a specific start and end time, by the day of the week or any combination.

DATE

START DATE: END DATE:

TIME

ALL DAY

START: HOUR: MINUTE: End: HOUR: MINUTE:

DAY OF WEEK

SUNDAY

MONDAY

TUESDAY

WEDNESDAY

THURSDAY

FRIDAY

SATURDAY

Alert Journal

The Alert Journal will show the history of the alert and the actions taken both by the system and by the user. Additionally, a user can add a journal entry to update status or actions taken.

To add an Alert Journal:

- Click the Pause button to stop the automatic refresh
- Expand the Alert you want to add an entry to by clicking the expand icon
- Click the Journals Button
- Type the journal entry into the text box where it says NEW JOURNAL ENTRY
- When done Click Add
- Click the Play button to stop the pause and allow to refresh

The screenshot shows the Alert Analyzer interface. At the top, it displays 'ALERT ANALYZER' and 'Displaying 1 - 10 of 3,898 Alerts'. Below this, there are controls for 'FILTERS', 'SORT', 'BULK DISPOSITION', and 'STATUS'. The main area shows a table of alerts with columns for DATE, NODE, POLICY, RULE, STATUS, and OWNER. A detailed view of an alert is shown, including a 'DETAILS' tab and a 'JOURNALS' tab. The 'JOURNALS' tab shows a table of journal entries with columns for TIMESTAMP, CREATOR, and ACTION. The 'OUTPUT' section at the bottom shows the alert details in a structured format.

DATE	NODE	POLICY	RULE	STATUS	OWNER
07/08/18 12:00:40 PM	devparb	Cisco HCS PCA	RTMT_ALERT	OPEN	Unassigned

TIMESTAMP	CREATOR	ACTION
07/08/18 12:45:36 PM	system	Alert Created. Response: Default RIP Schedule: autogenerated_schedule_24x7 Node: devparb(127.0.0.1) - Critical Cisco Error : Critical Cisco Error (<13>Jul 8 2018 17:00:40 169.254.5.16: <186>206881: : 203794: astdc-v-ocm-pub.dimensiona.com: Jul 08 2018 05:00:37 PM.410 UTC : 40C_RTMT-2-RTMT_ALERT: %[AlertName=CriticalServiceDown][AlertDetail=#012 Service operational status is DOWN.#012Cisco CallManager.#012The alert is generated on Sun Jul 08 12:00:37 CDT 2018 on node astdc-v-ocm-pub.dimensiona.com.][AppID=Cisco AMC Service][ClusterID=][NodeID=astdc-v-ocm-pub]: RTMT Alert)
07/08/18 12:45:37 PM	system	Incident Response - Method: ALERT, Status: Success
07/08/18 12:45:37 PM	system	Incident Response - Method: CONTROL, Description: New Vodafone Control, Status: Success

Alert Sorting

The alerts shown on the Alert Analyzer can be sorted based on three categories:

- Time to Expire / Escalate
- Alert Severity
- Alert Date & Time

These three choices determine the sorting of the alerts on the Alert Analyzer screen. Each one can be toggled between ascending and descending order. Additionally, the order of each one will be the first to last in priority. This can be changed by clicking the down or up button next to each category.

The screenshot shows the ALERT ANALYZER interface. At the top, it displays 'Displaying 1 - 10 of 3,698 Alerts'. Below this, there are controls for 'FILTERS', 'SORT', 'BULK DISPOSITION', and 'STATUS'. A dialog box is open over the 'SORT' controls, allowing selection of sorting criteria: 'TIME TO EXPIRE/ESCALATE', 'ALERT SEVERITY', and 'ALERT DATE & TIME'. Each criterion has 'ASCENDING' and 'DESCENDING' options, along with up and down arrow icons. 'CANCEL' and 'UPDATE' buttons are at the bottom of the dialog. The main table below shows a list of alerts with columns for 'STATUS' and 'OWNER'. The first row shows 'Error' and 'OPEN' status, 'Unassigned' owner, and a detailed alert message. Subsequent rows show 'Catch all test' and 'Cisco Alerts : Universal' categories, all with 'OPEN' status and 'Unassigned' owners. Each row includes a timestamp, a severity icon (red triangle), and an 'OUTPUT' section with detailed log data.

3.1.4. Search

Event Search


The Event search view provides access to all the raw data coming into Arbitrator Correlation and provides a simple interface to search and display it. The Arbitrator Correlation platform builds a dictionary of all of the words it has absorbed from all of the logs it has received and enables rapid search across large volumes of data. Essentially making an otherwise difficult amount of data quickly searchable and more useable.

Simple Searching

To perform a simple search across all of the logs based on the default time of “Last 24 Hours” use the “*” wildcard character.

- In the search text input field type *
- Press Enter or click the magnifying glass icon

All log data received in the last 24 hours will be returned. The default number of logs per page is 10 but can be expanded by opening the drop-down box under the time bar and selecting the number desired.



Keyword Searching

To perform a keyword search across all of the logs based on the default time of "Last 24 Hours" start by typing in the word that you know is present in your data, such as "Cisco". As you type the word the event search will begin to auto suggest your keyword based on the data the Correlation platform has collected. Once you have finished press enter, select the word in the drop-down list or click the magnifying glass icon.

All log data that contains the keyword in the last 24 hours will be returned. The default number of logs per page is 10 but can be expanded by opening the drop-down box under the time bar and selecting the number desired.



Utilizing Conjunctions with Searching

The Event Search allows the use of conjunctions to combine keywords which will assist you in being more specific in your search. The conjunctions available are AND, OR and NOT. To perform a search with conjunctions across all of the logs based on the default time of “Last 24 Hours” start by typing in the word that you know is present in your data, such as “Cisco”, followed by the conjunction then the next word. Once you have finished press enter, select the word in the drop-down list or click the magnifying glass icon.


All log data that contains the keywords in the last 24 hours will be returned. Note: when using a conjunction in the search the logic must match or no data will be returned. The default number of logs per page is 10 but can be expanded by opening the drop-down box under the time bar and selecting the number desired.



Date Range Searching

With any of the above methods the user can also select the specific date to search for the data. The default is the last 24 hours but by opening the drop-down bar several options are presented.

- Last 24 Hours: The default
- Last 1 Hour
- Last 30 Minutes
- Last 5 Minutes
- Custom date range showing from and to. Clicking in the “From” box opens up a calendar from where you can select the specific from date you desire. Clicking in the “To” box will do the same.



Search Result Meta-Data


The Event Search engine utilizes the core processes of the Arbitrator Correlation platform to store, tag and manage the data. To the right of each log entry is a blue “XML”. Clicking on this will open up all of the XML representation of the data along with some very important added elements. In particular are the Entity ID’s which server as the basis for making every event unique and formulating the “Reference ID” seen in the Alert Analyzer screen. Additionally, if applicable, a hash of the raw log is available for compliance purposes. To go back to the main search screen simply click the blue “Raw”.



3.1.5. Call Path

Call Path Monitor

The Call Path Monitor serves as one of the base screens for managing Unified Communications and the particular call path that a Voice over IP call takes. It will display the paths or routes that a call took from the source to the destination. Each path contains the IP Addresses, number of hops, delay and latency during the call.



Sorting Call Paths

The screen and the represented call paths can be sorted by three variables:

- Total Delay: The total latency on the call.
- Average Delay: The average latency on the call.
- Total Hops: The total number of layer-3 hops the call took.


Each selection also has the choice of selecting ascending or descending order.



Time Range for Call Paths

This provides the option of selecting the time range in which to show the call paths collected. Click the “Range” drop-down button. The available options are:

- All
- 1 Day
- 2 Days
- 3 Days
- 4 Days
- 5 Days




Expanding Call Paths

Expanding a call path allows you to see the path by hop or by IP Address. In addition, it provides an option to view it by the total per hop or cumulative delay, latency, and Jitter. The expanded view also shows you whether the call was ON Network or OFF Network. The expanded view can be toggled to show in graph or table views.

To expand a call path and toggle between graph and table views:

- Click arrow icon next to the call path you want to expand

By default, the view will be in graph mode. To switch to the table view, simply choose the table view icon in the upper left corner of the now expanded call path.



Searching Call Paths

Each Call Path has several fields you can utilize to search and filter for the call(s) that you are interested in. The fields available are:

- Source
- Destination
- Method
- Hops

The screenshot shows a search filter dialog box. At the top, there is a search bar with the text 'search' and a search icon. Below the search bar, there are four checkboxes, all of which are checked:

- SOURCE
- DESTINATION
- METHOD
- HOPS

Each checkbox is accompanied by an empty text input field. At the bottom of the dialog, there are two buttons: 'CLOSE' and 'SEARCH'.


View Call Details from the Call Path

The Call Path screen allows you to drill into the specific call details right on the chart. Simply click the blue telephone icon at the end of the path and it will take you to the Call Details Explorer view for that call path.

3.1.6. Call Details

Call Details Explorer

The Call Details Explorer is the main screen for managing Unified Communications and the details of a particular call path that a Voice over IP call takes. It will display the time, source destination, vendor, latency and hops along the top screen. Below will show the Call path with each hop along with the call metrics (packets lost, jitter, R-Factor and MOS).




Filter by Date and Time


In the upper left corner there is a time bar. You can choose to search the call details by the various options presented. When you click inside the bar several options along with a calendar open up to select.

- Last 5 Minutes
- Last 30 Minutes
- Last Hour
- Last 12 Hours
- Last 24 Hours
- Last 7 Days * This Month
- Last Month

- Last 2 Months
- Last 3 Months
- Last 6 Months
- Last Year
- Specific Date and Time




Filter by Call Quality



Just next to the time bar are several icons that allow you to filter the call detail data by Call Quality. There are 3 options:

- Bad Calls (Red)
- Good Calls (Green)
- Bad and Good Calls (Blue)

Clear Filter, Update and Delete Call




The three icons next to the call quality filters provide the functions below:

- Clear Filter: This will remove all filters set and the call details will show the default display.
- Update: The screen is pre-set with a refresh timer. Clicking this icon allows you to request new data on demand.

- Delete Call: If the check box is selected next to any call then by clicking this icon the system will delete that call.

Refresh Pause

Selecting the pause icon in the top left of the view will stop the refresh cycle. This comes in handy as you are reviewing a specific call.




Sorting

At the top right of the screen is a drop-down button called "Sort". Clicking this button will open up several options for which the call details can be sorted.

- Time: The time the call was placed
- Source: The source that placed the call
- Destination: The destination of the call
- Vendor: Identifies the method that created the call. The only options are LX1 (the VOSS Raptor Call Path generator) and RTCP (Avaya specific RTCP and call path data)
- Latency: The aggregate latency recorded on the call
- Hops: The total number of hops the call took


Each option allows for the choice of ascending or descending order.



Search Call Details


The search bar in the top right of the screen allows the user to search for specific call details. There are three options that can be utilized to search:

- Source: The source IP that made the call
- Destination: The destination IP that received the call
- Vendor: Identifies the method that created the call. The only options are LX1 (the VOSS Raptor Call Path generator) and RTCP (Avaya specific RTCP and call path data)



3.1.7. Call Management Configuration

In very busy or large environments it is imperative to manage the data that is being collected in the Call Detail Explorer. Have potentially 100's of thousands of calls can lead to the data becoming difficult to manage. As such there is the option to manage the configuration of the call table within the Call Detail Explorer screen. Click the file cabinet icon next to the search bar and a menu screen will pop up. This provides optional time and methods for which the call data can be archived. The choices are Daily, Weekly, Monthly or Quarterly. Be sure to toggle on "Alert on Archive Failure" and "Alert on Archive Success. The methods available for archival are SCP, SFTP or SMB. Each requires a host, path and credential. Multiple methods may be added.



4. Configuration

4.1. Introduction to Arbitrator System Configuration

4.1.1. Overview

Insights Arbitrator's **Configuration** GUI is accessible via the toolbar **Spanner** icon (System Configuration), on the main user interface.



The **Configuration** GUI toolbar icons provide access to configuration options for the following:

- *Policy Configuration*
- *Asset Configuration*
- *Probe Configuration*
- *Controls*
- *Response Procedure Configuration*
- *Credential Configuration*
- *Customer Configuration*
- *Access Control*
- *Import & Export*
- *Archive Management*
- *Tools*

The screenshot displays the V OSS Policy Configuration interface. On the left, a 'Policies' sidebar lists several policies with their respective counts: Cuom_CmCat_Cm (146), Touy (5), Ack Alert (2), Demo2 (1), Infinity (1), Ping (1), and Second Dchannel (1). The main area shows a 'Rules' table with columns for Name, Threshold, Window, Severity, and Response Procedure. The rules listed are:

Name	Threshold	Window	Severity	Response Procedure
Alarm ID: 50506 (DChannelO...	1 time	1 minute	Critical	Default IRP
Alarm ID: 50500 (CallManag...	1 time	1 minute	Critical	Default IRP
Alarm ID: 50501 (SDLLinkSV)	1 time	1 minute	Minor	Default IRP
Alarm ID: 50502 (SDLLinkOO...	1 time	1 minute	Critical	Default IRP
Alarm ID: 50503 (CMVersion...	1 time	1 minute	Informational	Default IRP

4.2. Policy Configuration

4.2.1. Overview

Policies are a modular groupings of correlation rules, actions and response procedures that define how to respond to certain situations that happen on the monitored systems. Policies are usually system and manufacturer specific but can contain custom scripts for actions and response procedures. Each policy will also contain several correlation rules that are designed to create Alerts based on the best practices of that particular system manufacturer. These alerts can apply to:

- Business Processes
- Infrastructure
- Security
- Applications
- Unified Communications
- Network behavior
- Metrics and Threshold Violations

This screenshot is identical to the one above, showing the V OSS Policy Configuration interface with the same list of policies and rules.

4.2.2. Correlation Rules

A Correlation rule extracts data from the various sources and then defines the parameters for Alert creation within a Policy. It may contain 1 or more Correlation Definitions along with specific actions and Response Procedures. Each correlation rule consists of the following parameters:

Parameter	Description
Name	Descriptive name for the correlation rule which will be displayed within an Alert and viewed in Alert Analyzer.
Description	Enter a complete description of the problem that created the alert along with any specific remediation steps that should be taken to resolve the problem.
Type	Simple: Select if the rule is to analyze a single log and as a result of the rule, you want to execute an action. Compound: Select if the rule is to correlate more than one log, the results of another correlated event or multi-tiered rules. A compound rule can be one or more simple rules that feed into one primary rule, or it can come directly from the source. Unique: Same as Simple but as a definition will be the only one.
Threshold	Selects how many times this rule is to match before an action occurs.
Window	Select the time window for the rule to match before an action occurs.

Parameter	Description
Severity	Indicates what is to appear in the Status field on the Alert Viewer monitor. Select the severity for this rule: <ul style="list-style-type: none"> • Informational • Minor • Major • Critical
Action	Choose the action that is to occur for this rule, based on the selection in the Severity field <ul style="list-style-type: none"> • Respond - If the condition is met, set a marker and send an alert. • Track - If the condition is met, track the event, but do not post it to the Alert Analyzer. • Track/Respond - If the condition is met, send an alert and continue to monitor. • Respond on Expire – If the condition is met, wait to send an alert until the window time has expired. If you want the policy/rule to only alert after an application does not respond, based on the setting (for example, to ping 9 times in 10 minutes), choose Track and Respond. For the example in this case, the alert triggers as soon as it sees 9 ping failures. This setting (Respond on Expire) does not track. • Submit - Submit the results of a correlation event back into the Correlation Engine so that the behavior can be analyzed and re- correlated. • Submit/Respond - Submit this alert back into the Correlation Engine so that the event can be analyzed and re-correlated. Then set a marker and send an alert.
Response Procedure	For any rule that is satisfied, an Incident Response Procedure occurs and an event is posted to the Alert Analyzer. Select the Response Procedure from the drop-down menu to execute when conditions have been met.
Definition Output	Selects a single Correlation Definition's extracted value to be displayed with the Alert.
Enabled	Toggle to enable/disable the rule
Inherit Output	Toggle to enable/disable whether the rule will include the results of the filter attached to the policy module.
Halt Processing	Toggle to halt processing of logs to any other rules within the policy if the rule matches. This will highlight the Policy in Green to indicate that this function is in use.
Correlation Definitions	Click the wrench icon where you can define one or more definitions match and or extract the required data from a log or event. See Correlation Definitions.
Output Order	Sets the preferred order to output the extracted data from the Correlation Definitions.
Done	Click the Done box when the rule is complete
Save	Be sure to click the Save button so your rule (or changes) are saved and committed.

The screenshot displays the 'POLICY CONFIGURATION' interface. On the left, a list of policies is shown with checkboxes and fallover values. The 'Rules' tab is active, showing a configuration for a rule named 'Jitter Value Exceeded'. The configuration includes fields for Name, Description, Type (Simple), Action (Respond), Threshold (1), Window (1 minute), Severity (Critical), Response Procedure (LinkCallToAlert), Definition Output, Enabled (checked), Inherit Output (checked), and Halt Processing (checked). A 'Save' button is visible in the top right corner.


Policies	Name	Fallover
<input type="checkbox"/>	Aria	1
<input type="checkbox"/>	Aspect UFP System Alerts	2
<input type="checkbox"/>	Asset Log Monitor	1
<input type="checkbox"/>	Aways Call Monitor	4
<input type="checkbox"/>	Aways PDS SNMP Alarms	4
<input type="checkbox"/>	Aways PDS SYSLOG Alarms	13
<input type="checkbox"/>	Cisco Call Monitor	4
<input type="checkbox"/>	LAYERX Agent Monitor	3
<input type="checkbox"/>	Log Monitor	1
<input type="checkbox"/>	LXI Call Monitor v2	5
<input type="checkbox"/>	LXI SIP Call Errors v2	4
<input type="checkbox"/>	Nortel Call Monitor	3
<input type="checkbox"/>	SRG Monitor	1

Rules	Name	Threshold	Window	Severity	Response Procedure
<input type="checkbox"/>	Jitter Value Exceeded	1	1 minute	Critical	LinkCallToAlert

Correlation Filters provide a simple way of ensuring that all of the correlation rules within the policy are firing on the correct set of data. The engine first looks at the filter criteria, then it selects only the data that matches the criteria, and then it applies the correlation rule. You can add as many of these as required.

Each filter has the following options:

Filter Option	Description
Name	Provide a name as close as possible to the data elements you wish to filter. This allows the output to match the name once viewed in the alert text.
Pattern	<p>The extraction method used to pull a particular data point out. Click the Wrench icon adjacent to the box to launch the Regex Wizard, which helps you to find and extract the data.</p> <p>The Regex Wizard has two sections:</p> <ol style="list-style-type: none"> 1. Select a Log: In the top section you can search and select the log or data set you will be utilizing. That will then show up in the bottom portion under the phrase "Select log from the list above or paste log here:". You can copy and paste a log into this section as well. 2. Create Regex: Once you have your log then go to this section. Here you can use the wizard to create the Regular Expression required. Close the wizard and copy this pattern the Regex into the box under Pattern.
Source Field	From the drop-down, choose the source from which data is extracted.
Pattern Type	<p>From the drop-down, choose the type of expression you want to use:</p> <ul style="list-style-type: none"> • String Match • Regular Expression Match • Regular Expression Match/Extract (Most Often Used) • Regular Expression Multi-Valued Extract
Function	<p>If the extracted data is integer-based, you can apply the following functions for comparing data:</p> <ul style="list-style-type: none"> • None • Greater Than • Less Than • Same
Value	This field is available only if the data extracted is an integer.



4.2.3. Example - Policies and Alerts

Let's say you have a Ping policy that you've set to alert after 10 failures in 20 minutes.

Depending on how you've set up your rules, the following may occur:

- The policy may run against all your assets and trigger an alarm if the cumulative Ping failure (across all assets) hits 10
- The policy may trigger an alarm for each asset that fails a ping 10 times in 20 minutes

Thus if it sees 10 failures (across all assets) in 20 minutes, an alert is triggered. However, if you want 10 failures per asset, you need a definition for the IP address, and set the filter function to **Same**, which defines that when you see 10 failures for the same IP address, trigger an alert.

You can configure this definition in two ways:

- As a filter on the policy
- As a specific rule definition.

4.2.4. Correlation Definitions

A Correlation Definition defines what criteria to match within the data. Each definition will consist of the following parameters:

Parameter	Description
Name	<p>Name this as close as possible to the data elements being extracted. That way the output matches the name once viewed in the alert text. It is also utilized in the key value pair within the alert text.</p> <p>This is the extraction methodology utilized to pull the particular data point(s) out. Simply find the log containing the data by utilizing the search bar above. Within that log you can highlight the text you want to extract. Once highlighted a box will pop up allowing you to name the field and extract it. This will automatically create the Regex to extract the data. The highlight method is about 95% accurate.</p> <p>If you have trouble with this method due to special characters in the data set, then you can utilize the “wrench” icon beside the Pattern box and it will bring up the “Regex Wizard” to assist in finding and extracting the data.</p>
Pattern	<p>Within the Regex Wizard there are 2 sections:</p> <ul style="list-style-type: none">• Select a Log: In the top section you can search and select the log or data set you will be utilizing. That will then show up in the bottom portion under the phrase “Select log from the list above or paste log here:”. As the phrase indicates you can copy and paste a log into this section as well.• Create Regex: Once you have your log then go to this section. Here you can utilize the wizard to create the Regular Expression required. Close the wizard and copy this pattern the Regex into the box under Pattern.

Parameter	Description
Source Field	In the drop-down box select the source from which the data is being extracted.
Pattern Type	<p>Select from the drop-down box the type of expression you want to utilize:</p> <ul style="list-style-type: none"> • String Match • Regular Expression Match • Regular Expression Match/Extract (Most Often Used) • Regular Expression Multi-Valued Extract <hr/> <p>Note: The “Extract” pattern types above will cause the correlation engine to include the definition name and the matched value in the Alert Message.</p> <hr/>
Function	<p>The functions below may be used to change what the correlation engine counts as a “match” in the log. Alerts are only triggered if the specific number of matches are found.</p> <ul style="list-style-type: none"> • None - Default. Only use Pattern type matching to trigger a match. • Greater Than - Should only be applied to integer values. If the extracted value is greater than the configured value, then a “match” is made. • Less Than - should on be applied to integer values. If the extracted value is less than the configured value, then a “match” is made. • Same - Can be applied to both Text or Integer. If the extracted value is the same as previous occurrences, a match triggered. For example, if multiple devices are sending an error message, only the first error will trigger an alert. If the desired goal is to trigger an alert for unique IP address, then the IP address definition should have the Same function applied.
Value	This field will only be available if the Function selected is either “Greater Than” or “Less Than”.

RULE DEFINITIONS » Jitter Value Exceeded

Changes made Cancel Update

0800 Last 24 Hours -

Click here for help building rules Build a New Definition Manually

Displaying 1 - 10 of 154,942 events < first prev next last > 10 1

Events CALL_METRICS_ID Start CALL_ID

Source Field Raw Log

```
1 07/11/18 16:54:10 PM <13-Jul 11 2018 21:51:01 logger: {"CISCO_RPMV_SERVICE": {"Timestamp":1531345822,"NumOfHosts":1,"ReturnCode":0,"ErrorMessage":"","AMC":"CUCK12","RtLoc":"CUCK12","AssetName":"10.13.37.43","AssetHostName":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","Name":"CUCK12","ServiceName":"Cisco Trace Collection Service","ElapsedTime":2958219, "Host":127.0.0.1 Port:devlog Method:}}>
```

Extract Field

Name this field: IP Address

Cancel Save

```
2 07/11/18 16:54:10 PM <RETURNMSG>Socket Created. Socket Connected. </RETURNMSG>
```

```
3 07/11/18 16:54:10 PM <RETURNMSG>PHP Fatal error: Uncaught SoapFault exception: [HTTP] Unauthorized in /part2/jail/arbitrator/modules/exec/cisco/axlGetPhoneInventory_creds.php:88 Stack trace: #0 [internal function]: soapClient->doRequest('<?xml version='...', 'https://10.13.3...', 'http://schemas...', 1, 0) #1 /part2/jail/arbitrator/modules/exec/cisco/axlGetPhoneInventory_creds.php(88): SoapClient->call('SelectCDevice', Array) #2 /part2/jail/arbitrator/modules/exec/cisco/axlGetPhoneInventory_creds.php(88): SoapClient->SelectCDevice(); Array) #3 [main] thrown in /part2/jail/arbitrator/modules/exec/cisco/axlGetPhoneInventory_creds.php on line 88 </RETURNMSG>
```

RULE DEFINITIONS » Jitter Value Exceeded

Please fill in all Name and Pattern fields Cancel Update

0800 Last 24 Hours -

Click here for help building rules Build a New Definition Manually

Displaying 1 - 10 of 154,942 events < first prev next last > 10 1

Events CALL_METRICS_ID Start CALL_ID

Name (new)

Source Field Raw Log

Pattern Type Function Value

Regular Expression Match/Extract None

```
1 <13-Jul 11 2018 21:51:01 logger: {"CISCO_RPMV_SERVICE": {"Timestamp":1531345822,"NumOfHosts":1,"ReturnCode":0,"ErrorMessage":"","AMC":"CUCK12","RtLoc":"CUCK12","AssetName":"10.13.37.43","AssetHostName":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","Name":"CUCK12","ServiceName":"Cisco Trace Collection Service","ElapsedTime":2958219,"ServiceStatus":1}}>
```

Extracted Value:

Regex Wizard Cancel Update

1) Select a Log 2) Create Regex

Search for logs: Last 24 Hours -

Displaying 1 - 10 of 2,961,353 events < first prev next last > 10 1

```
<?xml version='1.0' encoding='UTF-8'><!-- @(#) 13-Jul-11 2018 21:51:01 logger: {"CISCO_RPMV_SERVICE": {"Timestamp":1531345822,"NumOfHosts":1,"ReturnCode":0,"ErrorMessage":"","AMC":"CUCK12","RtLoc":"CUCK12","AssetName":"10.13.37.43","AssetHostName":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","Name":"CUCK12","ServiceName":"Cisco Trace Collection Service","ElapsedTime":2958219,"ServiceStatus":1}}>
```

Select log from the list above or paste log here:

```
<?xml version='1.0' encoding='UTF-8'><!-- @(#) 13-Jul-11 2018 21:51:01 logger: {"CISCO_RPMV_SERVICE": {"Timestamp":1531345822,"NumOfHosts":1,"ReturnCode":0,"ErrorMessage":"","AMC":"CUCK12","RtLoc":"CUCK12","AssetName":"10.13.37.43","AssetHostName":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","AssetDescription":"","AssetIpAddress":"10.13.37.43","Name":"CUCK12","ServiceName":"Cisco Trace Collection Service","ElapsedTime":2958219,"ServiceStatus":1}}>
```

Regex Wizard Cancel Update

1) Select a Log 2) Create Regex

WHERE DOES THE MATCH BEGIN?

Include the text that precedes the match? If so, enter it here or else leave this field blank.

LIST ALL PHRASES YOU ARE TRYING TO MATCH

Include the text that follows the match? If so, enter it here or else leave this field blank.

WHERE DOES THE MATCH END?


Include the text that follows the match? If so, enter it here or else leave this field blank.

REGEX GENERATED

4.2.5. Add a Policy

To add a policy:

1. Click the Policy View from the Configuration Menu Bar at the top of the page.
2. Click the Plus Icon at the bottom left of the Policies panel
3. Fill in the Policy name and press enter.



4.2.6. Add a Correlation Rule

To add a new correlation rule:

1. Click the Policy to which you wish to add the rule.
2. Click the Plus icon at the bottom of the Rules panel.
3. Fill in the rule name and the parameters.

The screenshot displays the 'POLICY CONFIGURATION' interface. On the left, there is a 'Policies' list with various monitoring rules like 'Avaya POS SMDP Alarms' and 'Cisco Call Monitor'. The main area shows a 'Rules' table with columns for Name, Threshold, Window, Severity, and Response Procedure. Below the table, a detailed configuration form for a rule is visible, including fields for Name, Description, Type, Threshold, Window, Severity, Action, Response Procedure, Definition Output, Enabled, Inherit Output, and Halt Processing. The 'Name' field contains 'new' and the 'Severity' is set to 'Informational'.

4.2.7. Add a Definition

To add a new definition:

1. Click the wrench icon within any rule to bring up the search engine.
2. Enter a search term that is relevant or is in the log that you would like to match and press Enter. This will return the last 10 logs with this term in them.
3. Utilize the highlight and extract procedure or the Regex Wizard as described in the in “Correlation Definitions” section above.
4. Once finished click Update in the top right of the screen and be sure to save your Definition on the next page.

4.2.8. Delete a Correlation Rule

To delete a correlation rule:

1. Click the policy name on the left side of the screen.
2. Click the check box on the Correlation rule you wish to delete.
3. Click the minus icon at the bottom of the correlation panel.
4. Click the Save icon in the upper right to save your change.

The screenshot displays the 'POLICY CONFIGURATION' interface with the 'Rules' tab selected. The interface is divided into two main sections: 'Policies' on the left and 'Rules' on the right. The 'Policies' section lists various monitoring policies with checkboxes and counts. The 'Rules' section displays a table of correlation rules with columns for Name, Threshold, Window, Severity, and Response Procedure. A 'Save' button is located in the top right corner. At the bottom of the Rules panel, there are navigation icons including a minus sign. A blue arrow points to the 'Save' button, another blue arrow points to the minus icon, and a third blue arrow points to the check box next to the 'DISREGARD - UnableToRun' rule.

Name	Fallover	Name	Threshold	Window	Severity	Response Procedure
<input type="checkbox"/> Cisco Call Monitor	<input checked="" type="checkbox"/> 4	<input type="checkbox"/> CLEARED - RPTR Alarm	1 0me	1 minute	Informational	AlertClear
<input type="checkbox"/> LAYERX Agent Monitor	<input checked="" type="checkbox"/> 3	<input type="checkbox"/> CRITICAL - RPTR Alarm	1 0me	20 minutes	Critical	AlertHold
<input type="checkbox"/> Log Monitor	<input checked="" type="checkbox"/> 1	<input type="checkbox"/> DISREGARD - FailedNodes	1 0me	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LXT Call Monitor v2	<input checked="" type="checkbox"/> 5	<input checked="" type="checkbox"/> DISREGARD - UnableToRun	1 0me	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LXT SIP Call Errors v2	<input checked="" type="checkbox"/> 6	<input type="checkbox"/> INDETERMINATE - RPTR Ala...	1 0me	15 seconds	Informational	DoNotAlert
<input type="checkbox"/> Nortel Call Monitor	<input checked="" type="checkbox"/> 3	<input type="checkbox"/> ISG Alarm trap - INDETERM...	1 0me	1 minute	Informational	DoNotAlert
<input type="checkbox"/> PING Monitor	<input checked="" type="checkbox"/> 2	<input type="checkbox"/> ISG Alarm trap - MAJOR	1 0me	1 minute	Major	DoNotAlert
<input type="checkbox"/> Powerwave SHWP Alarms	<input checked="" type="checkbox"/> 11					
<input type="checkbox"/> Silo training policy	<input type="checkbox"/> 2					
<input type="checkbox"/> Test Alarm v1	<input type="checkbox"/> 1					
<input type="checkbox"/> AJ Experimental	<input checked="" type="checkbox"/> 3					

4.2.9. Delete a Policy

To delete a policy:

1. Click the check box next to the name of the Policy you wish to delete.
2. Click the minus icon in the bottom left of the policy panel.
3. Click the Save icon in the upper right to save your change.

The screenshot shows the 'POLICY CONFIGURATION' interface. On the left, there is a 'Policies' table with columns for Name, Fallover, and a checkbox. The 'Powerwave SNMP Alarms' policy is selected, and its name is italicized. On the right, there is a 'Rules' table with columns for Name, Threshold, Window, Severity, and Response Procedure. A blue arrow points to the 'Save' button in the top right corner.

Policies			Rules				
Name	Fallover		Name	Threshold	Window	Severity	Response Procedure
<input type="checkbox"/> Cisco Call Monitor	<input checked="" type="checkbox"/>	4	<input type="checkbox"/> CLEARED - RPTR Alarm	1 time	1 minute	Informational	AlertClear
<input type="checkbox"/> LAXDRX Agent Monitor	<input checked="" type="checkbox"/>	3	<input type="checkbox"/> CRITICAL - RPTR Alarm	1 time	20 minutes	Critical	AlertHold
<input type="checkbox"/> Log Monitor	<input checked="" type="checkbox"/>	1	<input type="checkbox"/> DISREGARD - FailedNodes	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LX1 Call Monitor v2	<input checked="" type="checkbox"/>	5	<input type="checkbox"/> DISREGARD - UnableToRun	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LX1 SIP Call Errors v2	<input checked="" type="checkbox"/>	6	<input type="checkbox"/> INDETERMINATE - RPTR Ala...	1 time	15 seconds	Informational	DoNotAlert
<input type="checkbox"/> Nortel Call Monitor	<input checked="" type="checkbox"/>	3	<input type="checkbox"/> ISG Alarm trap - INDETERMI...	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> PING Monitor	<input checked="" type="checkbox"/>	2	<input type="checkbox"/> ISG Alarm trap - MAJOR	1 time	1 minute	Major	DoNotAlert
<input checked="" type="checkbox"/> Powerwave SNMP Alarms	<input checked="" type="checkbox"/>	11	<input type="checkbox"/> ISG Alarm trap - MAJOR	1 time	1 minute	Major	DoNotAlert
<input type="checkbox"/> Site training policy	<input type="checkbox"/>	2					
<input type="checkbox"/> Test Alarm v1	<input type="checkbox"/>	1					
<input type="checkbox"/> AJ Exper/Mental	<input checked="" type="checkbox"/>	3					
<input type="checkbox"/> ALSTOYBARN : Alert Exa...	<input checked="" type="checkbox"/>	9					

4.2.10. Disable or Enable a Policy

To Disable and Enable a Policy:

1. Select the Policy by clicking the check box next to the name of the policy.
2. Click the Green Check Box at the bottom of the Policies listing column.
3. The Name of the Policy will become italicized indicating that the Policy is Disabled
4. To Enable the Policy: Click the Green Check Box again. The name will turn back to a normal font indicating it is enabled.

The screenshot shows the 'POLICY CONFIGURATION' interface. The 'Powerwave SNMP Alarms' policy is selected, and its name is italicized. A blue arrow points to the green checkmark at the bottom of the policy row. A yellow banner at the top indicates 'Changes have been made'.


Policies			Rules				
Name	Fallover		Name	Threshold	Window	Severity	Response Procedure
<input type="checkbox"/> Cisco Call Monitor	<input checked="" type="checkbox"/>	4	<input type="checkbox"/> CLEARED - RPTR Alarm	1 time	1 minute	Informational	AlertClear
<input type="checkbox"/> LAXDRX Agent Monitor	<input checked="" type="checkbox"/>	3	<input type="checkbox"/> CRITICAL - RPTR Alarm	1 time	20 minutes	Critical	AlertHold
<input type="checkbox"/> Log Monitor	<input checked="" type="checkbox"/>	1	<input type="checkbox"/> DISREGARD - FailedNodes	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LX1 Call Monitor v2	<input checked="" type="checkbox"/>	5	<input type="checkbox"/> DISREGARD - UnableToRun	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> LX1 SIP Call Errors v2	<input checked="" type="checkbox"/>	6	<input type="checkbox"/> INDETERMINATE - RPTR Ala...	1 time	15 seconds	Informational	DoNotAlert
<input type="checkbox"/> Nortel Call Monitor	<input checked="" type="checkbox"/>	3	<input type="checkbox"/> ISG Alarm trap - INDETERMI...	1 time	1 minute	Informational	DoNotAlert
<input type="checkbox"/> PING Monitor	<input checked="" type="checkbox"/>	2	<input type="checkbox"/> ISG Alarm trap - MAJOR	1 time	1 minute	Major	DoNotAlert
<input checked="" type="checkbox"/> Powerwave SNMP Alarms	<input checked="" type="checkbox"/>	11	<input type="checkbox"/> ISG Alarm trap - MAJOR	1 time	1 minute	Major	DoNotAlert
<input type="checkbox"/> Site training policy	<input type="checkbox"/>	2					
<input type="checkbox"/> Test Alarm v1	<input type="checkbox"/>	1					
<input type="checkbox"/> AJ Exper/Mental	<input checked="" type="checkbox"/>	3					
<input type="checkbox"/> ALSTOYBARN : Alert Exa...	<input checked="" type="checkbox"/>	9					

4.2.11. Clone a Policy

Cloning a policy allows the quick replication of all of the Correlation Policy rules and definitions. The user then can simply change only the required elements for the new policy.

To clone a policy:

1. Select the Policy by clicking the check box next to the name of the policy.
2. Click the Blue "C" Box at the bottom of the Policies listing column.
3. Rename the Policy and make your modifications.
4. Be sure to click Save to save the new policy.



4.2.12. Export or Import a Policy

The Arbitrator platform allows for full export / import of all of its configuration. Within the Policy Configuration section, you can export and import the policy that you exported from another system.

A new system log table `insights_system_log` has also been added to log user actions and a user can create a dashboard to view these actions.

See the:

Log Search Section in the Dashboard and Reporting Administration Guide.

+ Global Filters (0 applied)

[Click to Refresh Data](#)

Mar 9, 2022 9:09 am - Mar 9, 2022 10:09 am

System log							
Search							
	lxt timestamp epoch (America/Chicago)	username	action	area	status	duration	details
7	03/09/22 9:24:49 am	admin	import	asset	SUMMARY	19	{"csvRows":1, "numInsert":0, "numUpdate":2, "numDelete":0}
8	03/09/22 9:19:31 am	admin	import	asset	SUMMARY	13	{"csvRows":1, "numInsert":1, "numUpdate":0, "numDelete":0}
9	03/09/22 9:18:06 am	admin	export	asset	SUMMARY	0	{"csvRows":2}
4	03/09/22 9:27:56 am	admin	export	asset	SUMMARY	0	{"csvRows":3}
1	03/09/22 10:07:28 am	admin	import	policy	SUMMARY	1	{"csvRows":4, "numGroup":1, "updateRows":"1,2,3,4", "numUpdate":4}
5	03/09/22 9:26:24 am	admin	import	asset	SUMMARY	14	{"csvRows":6, "numInsert":0, "numUpdate":6, "numDelete":0}
10	03/09/22 9:13:30 am	admin	import	asset	SUMMARY	11	{"csvRows":6, "numInsert":1, "numUpdate":4, "numDelete":0}
6	03/09/22 9:25:13 am	admin	import	asset	SUMMARY	43	{"csvRows":6, "numInsert":1, "numUpdate":5, "numDelete":0}
3	03/09/22 10:03:12 am	admin	export	policy	SUMMARY	0	{"numExportPolicyGroups":1, "csvRows":4}
2	03/09/22 10:05:50 am	admin	export	policy	SUMMARY	0	{"numExportPolicyGroups":3, "csvRows":28}

Export a Policy

1. Select the check boxes of the policies to export, or select the **Name** check box at the top of the **Policies** list to select *all* policies.
2. Click the green Down arrow button at the bottom of the **POLICY CONFIGURATION** panel.
3. The **Export CSV** dialog opens. Enter a **CSV file name** (You do not have to add the .csv file extension) and click **Export**.
4. The **Export finished** dialog shows when the export file has been created. Click **Download** to save the CSV file to your selected download location.

Import a Policy

1. Click the green Up arrow button at the bottom of the **POLICY CONFIGURATION** panel.
2. A pop-up box will appear asking you choose your file.
3. Click the **Choose file** button and select the exported CSV file that you have saved to your computer.
4. Click the **Import** button.

Policy CSV Format

The following columns are in an exported CSV file:

```
"row action", "policy group name", name, description, type, action, severity,
"respond procedure", "SubCategory (definition: regular expression match)",
"Message (definition: regular expression match/extract)"
```


Note:

- The "row action" column is used when importing and if it contains "delete", then the row will be deleted upon import.
- The "respond procedure" column can be used when importing and should then contain the Response Procedure name *exactly* as it exists on the system. If a procedure is found, then it will be assigned

to the associated rule. If a new value is entered, a new Response Procedure is created. The default Response Procedure is used if no value is entered.

- The combination: “policy group name”, “name”, “respond procedure” should be unique in CSV row. If a policy found, its data will be updated. If not found, new policy will be inserted. The “name” has to be unique. If a rule is found, its data will be updated. If not found, new rule will be inserted to the policy indicated in “policy group name”.

See: [Response Procedure Configuration](#).



4.3. Asset Configuration

4.3.1. Overview

The Asset Configuration panel allows you to create Assets and Asset Groupings. Assets can be any devices that are either sending data or from which data is being retrieved. Each Asset can be assigned to a specific customer to create a multi-tenant environment.

A new system log table `insights_system_log` has also been added to log user actions and a user can create a dashboard to view these actions.


See the:

Log Search Section in the Dashboard and Reporting Administration Guide.

4.3.2. Add an Asset Group

To add a new asset group:

1. Click the Asset icon from the Menu bar.
2. Click the Plus icon in the bottom left corner of the Asset Groups panel.
3. Enter the Group name and press Enter.
4. Click the Save icon in the upper right.



4.3.3. Add an Asset to an Existing Group

To add a new Asset to a Group:

1. Click Asset Group to which you wish to add an asset.
2. Click the Plus icon at the bottom of the Asset panel.
3. An asset entry box will open up. Fill out all of the details for the asset under “Properties”.
4. Click the “Interface” tab and fill out the details, if applicable.
5. Click the check button to the right of the screen to add the asset.

The image displays two screenshots of the ASSET CONFIGURATION interface, showing the configuration of an asset.

Top Screenshot: Properties Tab

The interface shows a list of groups on the left and a table of assets. The selected asset is 10.1.1.1, with Asset Name AE_NAME and Description DESCD. The Properties tab is active, showing the following fields:


- Enabled:
- Maintenance Mode:
- IP Address:
- Asset Name:
- Description:
- Host Name:
- Type: Unknown (dropdown)
- Address:
- External URL:
- Model:
- Version:
- MAC Address:
- Alias:
- Manufacturer:
- Time Zone: UTC (dropdown)
- Customer:
- Site:

Bottom Screenshot: Interfaces Tab

The same asset is selected, and the Interfaces tab is active. The table below shows the interface configuration:

Name	IP Address	MAC Address	Vendor	Model	Version
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>


Note: Modification: If present, then more than one asset in more than one group can be modified when *modifying* assets. Change bars are displayed next to each asset and group when the assets or groups modified, for example:



4.3.4. Delete an Asset

To delete an Asset:


1. Click the Asset Group in which your Asset is located.
2. Click the “check” box next to the asset you wish to delete.
3. Click the “minus” icon within the Asset panel.
4. Click the “Save” icon in the upper right corner.



4.3.5. Delete an Asset Group

To delete an Asset Group:

1. Click the “check” box next to the Asset Group you wish to delete.
2. Click the “minus” icon in the bottom left of the Asset Group panel.
3. Click the “Save” icon in the upper right corner.



4.3.6. Assign a Probe to an Asset

A Probe is a script or set of commands that are saved in the system and can be utilized to gather data, issue commands to systems, auto repair or send data. Assigning a probe to an asset is typically done to retrieve data from that asset. Commands such as an SNMP GET or an API call are utilized to retrieve data from a particular asset.

To assign a Probe to an Asset:

1. Click the asset group and then click on the actual asset within that group that the Probe will run against.
2. Click the wrench icon, which will add a monitor profile to the asset.
3. The Probe Group (covered in the next section) screen is opened where you can select from all of the saved Probes in the system.

4. Select the desired Probe
5. Next click the green pencil icon, which will open up a profile to define the frequency the probe runs, the credentials needed for the probe to run, the schedule for the Probe to run and the choice to start it immediately.

Note: For SP25, the frequency for Polycom devices is set at 5 minutes.

6. Once complete click the check button to finalize the probe. This will take you back to the Asset screen and to the asset you had selected.

The image shows two screenshots from a web-based configuration tool. The top screenshot is titled "ASSET CONFIGURATION" and displays a table of assets. The bottom screenshot is titled "MONITOR PROFILE" and shows the configuration for a specific asset.

ASSET CONFIGURATION Table:

Groups	Assets	IP Address	Asset Name	Description	Type	Monitor Profile
Data Network (15)	<input type="checkbox"/>	192.168.1.3	Nortel_CS1K_BM	Nortel CS 1000 BM	Server voice	1 profile set
ETISALAT (1)	<input type="checkbox"/>	192.168.1.3	Nortel_CS1K_DAL	Nortel CS 1000 Dallas	Server voice	1 profile set
Genband (1)	<input type="checkbox"/>	192.168.1.3	Nortel_CS1K_SF	Nortel CS 1000 SF	Server voice	1 profile set
GreatWest (74)	<input type="checkbox"/>	192.168.1.3	Nortel_CS1K_SU	Nortel CS 1000 SU	Server voice	1 profile set
GROUP_NAME (1)	<input type="checkbox"/>	192.168.1.3	Nortel_CS1K_SW	Nortel CS 1000 SW	Server voice	1 profile set
LayerX (5)						
LayerX_Lab (12)						
LX1 Phones (2)						
Nortel (5)						

MONITOR PROFILE - Nortel_CS1K_BM Table:


Groups	Templates/Profiles	Name	Frequency	Credentials 1 & 2	Enabled
Probe Group	<input type="checkbox"/>	PING Probe	5 Minutes	None & None	<input checked="" type="checkbox"/>
AA (5)					
Application ssh probe (1)					
Aspect alarm demo (1)					
Aspect CallCenter Service Probes (3)					
Asset Probe Test (1)					
Avaya CDR Demo (1)					
Avaya CM SNMP Tables (1)					



4.3.7. Assign a Customer to an Asset

The Correlation Platform has multi-tenancy built in that provides the ability for different customers to see correlated or collected results of only their data. Within the configuration of assets, you can assign each asset to a specific customer. To assign a Customer to an Asset:


1. Click the asset group and then click on the actual asset within that group that is to be assigned to a Customer.
2. Click the pencil icon that will open up the details of that asset.
3. Click the field labeled Customer and a drop-down list of available Customers will appear.
4. Select the Customer that the asset belongs to and then click the blue check box in the top right.
5. Click the Save icon to save the changes.




4.3.8. Place an Asset in Maintenance Mode

The Correlation Platform allows any asset to be placed into Maintenance mode. Doing so will stop the platform from responding with alerts until it is removed from the mode. Data will still be collected but alerts will not be sent.

1. Click the asset group and then click on the actual asset within that group that is to be put into Maintenance mode.
2. Click the pencil icon that will open up the details of that asset.
3. Check the box next to the label Maintenance Mode and then click the blue check box in the top right.
4. Click the “plus” icon to return to the Asset Group and then click the “Save” icon to save the Maintenance Mode settings.



Assets in maintenance mode can be filtered by selecting **Maintenance** from the **Filter column** drop down list.



4.3.9. Export and Import an Asset

Within the **ASSET CONFIGURATION** section, you can export and import the asset that you exported from another system.

- When selecting asset groups, all assets belong to those groups will be selected (selecting individual assets will not take effect).
- If the **Group Name** checkbox is selected, all assets will be included - both **All groups** and **Ungrouped**.

Export an Asset

1. Select the check boxes of the assets to export, or select the **Group name** check box at the top of the **Groups** list to select *all* assets.
2. Click the green Down arrow button at the bottom of the **ASSET CONFIGURATION** panel.
3. The **Export CSV** dialog opens. Enter a **CSV file name** (You do not have to add the .csv file extension) and click **Export**.
4. The **Export finished** dialog shows when the export file has been created. Click **Download** to save the CSV file to your selected download location.

Import an Asset

1. Click the green Up arrow button at the bottom of the **ASSET CONFIGURATION** panel.
2. A pop-up box will appear asking you choose your file.
3. Click the **Choose file** button and select the exported CSV file that you have saved to your computer.
4. Click the **Import** button.


Asset CSV Format

The following columns are in an exported CSV file:

```
"Asset Name",Description,"IP Address","MAC Address",Vendor,
Model,Version,"Host Name",Alias,"Asset Group Name",
"Type of Device(see below)","Device's Timezone",Comments,
"Physical Address","Customer Name","Site Name","Row Action"
```

Note:

- The "Row Action" column is used when importing and if it contains "delete", then the row will be deleted upon import.
- Row uniqueness is the combination of: "IP Address", "Customer Name", "Site Name". If an asset found, its data will be updated. if not, new asset will be inserted under the asset group indicated in column "Asset Group Name".
- The column "Asset Group Name" has to be unique. if an asset group is found, its data will be updated. If not, a new asset group will be inserted.
- There are 2 entries in the import CSV:
 - An asset with data in all columns. Most important is the very first column "Asset Name".
 - An interface is a property of an asset. An interface only has data in from column "Description" to "Host Name". Most important is that it does not have data on the very first column "Asset Name". All CSV interface row(s) will be under an asset just right above it(them).



4.4. Probe Configuration

4.4.1. Overview

The Probes Configuration panel allows you to assign a group of scripts to an asset that can run on a set interval. These scripts will allow for data collection from many types of devices. The protocols can be API, SNMP or custom CLI scripts. SNMP v3 is also supported.

The return data from the Probes can then be injected into the system for correlation or can be stored in the database to allow for analysis on the Dashboard/Reporting server.


For PRI and SIP Trunk probes for Cisco Voice Gateways, reference:

Arbitrator Cisco PRI and SIP Probe Configuration

4.4.2. Add a Probe Group

To create a new Probe Group:

1. Click the Probe icon from the Menu bar.
2. Click the “Plus” icon within the Groups pane in the bottom left corner.
3. Enter the “Group” name and press Enter.
4. Click the “Save” icon in the upper right corner.



4.4.3. Clone a Probe Group

To clone an existing Probe Group:

1. Click the Probe icon from the Menu bar.
2. Select a Probe group to clone from.
3. Click the “C” icon within the Groups pane in the bottom left corner.
4. The cloned “Group” name shows: <source group name> clone. Modify this name to the required name.
5. Click the “Save” icon to save the added Probe.
6. The probes contained in this new group can also be modified. Refer to the steps to add, clone and modify probes.

The screenshot displays the Voss Probe Configuration interface. The top navigation bar includes the Voss logo, a warning icon, a globe icon, a person icon, a calendar icon, a search icon, a lock icon, a download icon, a trash icon, and a gear icon. The user is logged in as 'admin' and has 1684 days remaining. The main content area is titled 'PROBE CONFIGURATION' and features a 'Save' button in the top right corner. The interface is divided into two main sections: 'Groups' on the left and 'Probes' on the right. The 'Groups' section contains a list of groups with checkboxes and counts: 1-Cisco CUCM RIS CmDevice_creds (3), 1b-PING Monitor (1), 4-Cisco CUCM Version (1), 5-Cisco RTMT (1), 6.Cisco Expressway-API (2), 6a.Cisco Expressway Call Detail-API (1), 6b.Cisco Expressway - SNMP (2), 7.CUCM Perfmon AXL Counters (1), 8.Cisco Unity Perfmon AXL Counters (1), 9.Cisco IMP Perfmon AXL Counters (1), 9a.CUCM-END USER (1), and 9b.VOSS4UC (1). The 'Probes' section contains a table with columns for Name, Description, Unit, and Command and Parameters. The table lists three probes: RIS API data, SIP Trunk, and Media Resources. At the bottom of the 'Groups' pane, there is a toolbar with icons for minus, plus, 'C' (clone), refresh, upload, and download. A red arrow points from the word 'clone' to the 'C' icon in the toolbar.


Group Name	Count
1-Cisco CUCM RIS CmDevice_creds	3
1b-PING Monitor	1
4-Cisco CUCM Version	1
5-Cisco RTMT	1
6.Cisco Expressway-API	2
6a.Cisco Expressway Call Detail-API	1
6b.Cisco Expressway - SNMP	2
7.CUCM Perfmon AXL Counters	1
8.Cisco Unity Perfmon AXL Counters	1
9.Cisco IMP Perfmon AXL Counters	1
9a.CUCM-END USER	1
9b.VOSS4UC	1

Name	Description	Unit	Command and Parameters
RIS API data	phone, media resources, SIP ...		cisco/cucmrisphone/collectrisphones...
SIP Trunk			cisco/cucmrisiptrunk/collectrisiptru...
Media Resources			cisco/cucmrismediareources/collectr...

4.4.4. Create a Probe

To create a new Probe:

1. Click the group in which you wish to create a new Probe.
2. Click the Plus icon within the Probes panel.
3. Enter the name and description of the Probe.
4. De-select the check icon from the field titled "Custom". This field is utilized when putting a custom probe in place versus utilizing the ones within the system.
5. Select the Probe Category from the drop-down list. This will populate the scripts available in that category within the drop-down menu titled "Select Script".
6. Select a script from the script drop-down list.
7. Enter any additional information required by the selected script, such as the hostname, IP, etc.
8. Click the "Check" icon to close the probe in the far right of the Probe panel.
9. Click the "Save" icon to save the added Probe.



4.4.5. Clone a Probe


To clone a probe:

1. Click the probe which you wish to clone.
2. Click the “C” icon within the **Probes** panel.
3. The cloned “Probe” name shows: *<source probe name> clone*. Modify this name to the required name as well as any other properties you need to.
4. Select the **Done** checkbox before saving.
5. Click the “Save” icon to save the added probe.

4.4.6. Create a Custom Probe

To create a new Probe:


1. Click the group in which you wish to create a new Probe.
2. Click the Plus icon within the Probes panel.
3. Enter the name and description of the Probe.
4. Select and click the check icon from the field titled “Custom”. This field is utilized when putting a custom probe in place versus utilizing the ones within the system.
5. Enter the path and script that you wish to run.
6. Click the “Check” icon to close the probe in the far right of the Probe panel.
7. Click the “Save” icon to save the added Probe.



4.4.7. Delete a Probe Group

To delete a Probe Group:


1. Click the check box next to the group name you wish to delete.
2. Click the Minus icon within the Probe Group panel in the bottom left.
3. Click the “Save” icon to save the changes.



4.4.8. Delete a Probe

To delete a Probe:

1. Click the check box next to the Probe name you wish to delete.
2. Click the Minus icon within the Probe panel in the bottom right.
3. Click the “Save” icon to save the changes.



4.4.9. Export and Import a Profile

Important: This import/export is special. Since we do not have a Profile main screen, the import/export profiles are in Probe Configuration; the same as the legacy push button (right next import/export buttons).

Within the **PROBE CONFIGURATION** section, you can export and import the profiles that you exported from another system.

A new system log table `insights_system_log` has also been added to log user actions and a user can create a dashboard to view these actions.

See the:

Log Search Section in the Dashboard and Reporting Administration Guide.

Export a Profile

1. Click the Down arrow button at the bottom of the **PROBE CONFIGURATION** panel.
Since this is a probe configuration, we cannot select individual profiles, so it will export all profiles in the system.
2. The **Export CSV** dialog opens. Enter a **CSV file name** (You do not have to add the `.csv` file extension) and click **Export**.
3. The **Export finished** dialog shows when the export file has been created. Click **Download** to save the CSV file to your selected download location.

Import a Profile

1. Click the Up arrow button at the bottom of the **PROBE CONFIGURATION** panel.
2. A pop-up box will appear asking you choose your file.
3. Click the **Choose file** button and select the exported CSV file that you have saved to your computer.
4. Click the **Import** button.


Profile CSV Format

The following columns are in an exported CSV file:

```
"Row Action","Asset Name","IP Address","Customer Name",  
"Site Name","Probe Group Name","Credential 1 Name",  
"Credential 2 Name","Frequency (s)",Enable
```

Note:

- The "Row Action" column is used when importing and if it contains "delete", then the row will be deleted upon import.
- "Probe Group Name" must be unique.
- Combination: "IP Address","Customer Name","Site Name" must to be unique.
- "Asset Name" is used as a reference of the asset.
- When importing and if an asset and a probe group are found, then a profile will be updated/inserted. If not, nothing to import.



Assign a Probe to an Asset

A probe group assigned to an asset can be modified using a profile CSV file import by specifying the related “Asset Name” and “Probe Group Name” in the CSV file.

For example, consider an asset “Local System” that has 3 profiles:

MONITOR PROFILE > Local System

Groups		Templates/Profiles			
Probe Group		<input type="checkbox"/> Name	Frequency	Credentials 1 & 2	Enabled
» Cisco CUCM Version	1	<input type="checkbox"/> Local System Stats	1 Minute	None & touy	<input checked="" type="checkbox"/>
» Cisco Expressway	3	<input type="checkbox"/> Test Probe	1 Minute	None & loc	<input checked="" type="checkbox"/>
» Cisco Telepresence API - Call Details	1	<input type="checkbox"/> PING Monitor	1 Minute	ray & loc	<input checked="" type="checkbox"/>

We can assign probe “Cisco CUCM Version” to asset “Local System” as a CSV file import:

Row Action	Asset Name	IP Address	Customer Name	Site Name	Probe Group Name	Credential 1 Name	Credential 2 Name	Frequency (s)	Enable
	Local System	10.13.37.149			Cisco CUCM Version	ray	loc	60	TRUE

After importing, the profile is added to the probe group.

MONITOR PROFILE » Local System

Groups

Probe Group

- ▶ Cisco CUCM Version 1
- ▶ Cisco Expressway 3
- ▶ Cisco Telepresence API - Call Details 1

Templates/Profiles

<input type="checkbox"/> Name	Frequency	Credentials 1 & 2	Enabled	
<input type="checkbox"/> Local System Stats	1 Minute	None & touy	<input checked="" type="checkbox"/>	
<input type="checkbox"/> Test Probe	1 Minute	None & loc	<input checked="" type="checkbox"/>	
<input type="checkbox"/> PING Monitor	1 Minute	ray & loc	<input checked="" type="checkbox"/>	
<input type="checkbox"/> Cisco CUCM Version	1 Minute	ray & loc	<input checked="" type="checkbox"/>	

4.5. Controls


4.5.1. Overview

The Controls Configuration panel allows you to define a script or routine that can be executed by a response procedure or attached as a probe. These controls can be passed variables extracted from a correlation rule. The resulting return of the scripts execution can be mapped to the database, used as an action or can be injected back into the system to be correlated against another element.

4.5.2. Create a Control

To create a new Control:


1. Click the Plus icon within the control panel.
2. Enter the name of the Control.
3. De-select the check icon from the field titled "Custom". This field is utilized when putting a custom Control in place versus utilizing the ones within the system.
4. Click and Select from the categories dropdown list to populate the scripts dropdown.
5. Select a script from the script dropdown list.
6. Enter any additional information required by the selected script.
7. Click the Check icon to close the control in the far right of the control panel
8. Click Save icon.



4.5.3. Delete a Control

To delete a Control:

1. Click the check box next to the Control name you wish to delete.
2. Click the Minus icon within the Control panel at the bottom.
3. Click the "Save" icon to save the changes.



4.6. Response Procedure Configuration

4.6.1. Overview


The Response Procedure configuration panel allows you to define an automated response to a correlated event. Each Response Procedure can be assigned to one or more Correlation Rules while also containing and/or executing one or more of the following responses:

Action	Description
Alert	Visually show the alert in the alert views within the User Interface.
Email	An email will be sent to the recipients address and contain the Policy and Correlation Rule details that are triggered. Additionally, any data that is extracted from the correlated event will be included.
Control	Executes the selected Control Script as a result of the correlated event. Data from the correlated event will be passed to the script as well. These scripts can be utilized as run-book and/or automated remediation.
Forward	The forward allows the correlated event to be forwarded to another Arbitrator Correlation platform.

4.6.2. Create a Response Procedure

To create a response procedure:


1. Click the “Calendar” icon at the top of the Configuration panel.
2. Click the plus icon in the bottom left of the Response Procedure name panel. A box will open up where you can fill in the name of your response procedure.
3. The panel to the right is broken into two sections:
 - a. Response Procedure Details – This is the section that you select to add the elements defined in the table above.
 - b. Do Not Run Windows – Allows you to define certain date and times that you don’t want the system to take the actions within the Response Procedure.



4.6.3. Assign an Alert to a Response Procedure

To assign the Alert function to a response procedure:


1. Click the Alert check box in the top left of the Response Procedure Details panel.
2. If this system you are configuring is intended to be the redundant platform then click the Disable on Failover box to allow all data to flow but no actions to take place.








4.6.4. Delete a Response Procedure

To delete a Response Procedure:

1. Click the box next to the Response Procedure name.
2. Click the minus icon at the bottom of the Response Procedure name panel.
3. Click the Save icon to save your changes.



4.6.5. Enable ServiceNow Integration

<input type="checkbox"/> Name	Command and Parameters	Protection	
<input type="checkbox"/> LinkIPToAlert	LinkIPToAlert	Off	
<input type="checkbox"/> ReporterPush Reading	ReporterPush 172.30.15.121:65515 true	Off	
<input type="checkbox"/> ReporterPush-GC	ReporterPush 172.25.87.6:65515 true	Off	
<input type="checkbox"/> VpnSyslog	vpnSyslogAlert.sh	Off	
<input type="checkbox"/> <input type="text" value=""/>	<input type="checkbox"/> Custom	<input type="checkbox"/>	
Select Category <input type="text" value="ServiceNow"/>			
Select Script <input type="text" value="PushToServiceNow"/>			
Service Now IP Address / Hostname <input type="text" value=""/>			
Service Now Username <input type="text" value=""/>			
Service Now Password <input type="text" value=""/>			

1. Navigate to Configuration (cog icon) on the arbitrator.
2. Navigate to Control and click + to enter a new control.
3. In the **Name** text box enter ServiceNow.
4. Uncheck **Custom**.
5. Fill in the following details:
 - **Select Category:** ServiceNow
 - **Select Script:** PushToServiceNow
 - **Service Now IP Address / Hostname:**
 - **Service Now Username:**
 - **Service Now Password:**
6. Tick the blue tick box.
7. Click the **Save**.
8. Navigate to the Response Procedure Configuration menu.
9. Apply the control to the required IRP, such as the default IRP.

ServiceNow One Way Incident Integration

As the Correlation Platform detects new incidents a response procedure is defined to send the event into ServiceNow utilizing their API. Incident Response Procedures (IRP) are defined on an incident basis. Thus you can choose which events need to be sent to ServiceNow based on severity, type, threshold, or others. When the IRP kicks off it will create an event, insert the following fields and send it to ServiceNow:

- short description: Arbitrator Policy, Rule and Reference_Id
- description: full message from arbitrator
- severity: severity
- urgency: based on severity
- impact: based on severity
- category: software
- comments: full message from Arbitrator

ServiceNow Requirements

- ServiceNow URL
- ServiceNow User with SOAP API rights to insert Incidents
- ServiceNow Password

Arbitrator Correlation Configuration

- Version Required: 4.0001-15b
- Script: servicenow/PushToServiceNow.pl
- parameters:
 - URL_TO_SERVICENOW_INSTANCE
 - USERNAME
 - PASSWORD

ServiceNow images:

4.6. Response Procedure Configuration

The screenshot shows the ServiceNow incident form for incident INC0010023. The left sidebar contains navigation options like 'My Assets', 'Service Desk', and 'Incident'. The main form area includes fields for 'Configuration item', 'Assignment group', and 'Assigned to'. A 'Short description' field contains the text: 'LXTALERT: ARB_REFERENCEID=20000-01009001-00-01-7134-14 ARB_POLICY_MODULE=MultiTest ARB_CORRELATION_RULE=Some Rule'. Below this, there are sections for 'Automatic Replies (Out Of Office)', 'Firewall Rule Change', and 'About Windows 10'. The 'Notes' tab is active, showing a 'Watch list' and 'Work notes list'. An 'Activity' section displays a log entry from 'System Administrator' dated 2016-12-13 12:52:14, with details: Impact 1 - High, Incident state New, Opened by System Administrator, and Priority 1 - Critical.

The screenshot shows the ServiceNow Incidents list view. The table displays a list of incidents with columns for Number, Opened, Short description, Caller, Priority, State, Category, Assignment group, and Assigned to. The incident INC0010023 is highlighted.

Number	Opened	Short description	Caller	Priority	State	Category	Assignment group	Assigned to
INC0020001	2016-08-10 09:14:29	test	System Administrator	3 - Moderate	New	Inquiry / Help		2006
INC0010023	2016-12-13 12:52:14	LXTALERT: ARB_REFERENCEID=20000-01009001-00-01-7134-14 ARB_POLICY_MODULE=MultiTest ARB_CORRELATION_RULE=Some Rule		1 - Critical	New	Software		2012
INC0010022	2016-12-13 12:52:11	LXTALERT: ARB_REFERENCEID=20000-01009001-00-01-7134-16 ARB_POLICY_MODULE=MultiTest ARB_CORRELATION_RULE=Some Rule Major		2 - High	New	Software		2012
INC0010021	2016-12-13 12:52:08	LXTALERT: ARB_REFERENCEID=20000-01009001-00-01-7134-19 ARB_POLICY_MODULE=MultiTest ARB_CORRELATION_RULE=Some Rule Info		5 - Planning	New	Software		2012
INC0010020	2016-12-13 12:52:04	LXTALERT: ARB_REFERENCEID=20000-01009001-00-01-7134-18 ARB_POLICY_MODULE=MultiTest ARB_CORRELATION_RULE=Some Rule Minor		4 - Low	New	Software		2012

4.7. Credential Configuration


4.7.1. Overview

The Credentials configuration panel allows you to define and store credentials securely. These credentials can be assigned to a Probe or Control to allow for secure access to an asset, ticketing system or script. (See: Asset Configuration, Response Procedure Configuration)

4.7.2. Create a Credential

To create a Credential:

1. Click the “key” icon in the menu bar at the top.
2. Click the plus icon in the bottom left corner.
3. Enter the name to be assigned to the Credential.
4. Enter the Username and Password fields.
5. Click the blue check box.
6. Click the Save icon to save the credential.



4.7.3. Delete a Credential

To delete a Credential:

1. Click the check box to the left of the credential name you wish to delete.
2. Click the minus icon in the bottom left of the screen.
3. Click the Save icon to save your changes.



4.8. Customer Configuration

4.8.1. Overview


To enable multi-tenancy (assets, alerts and data) utilize the customer configuration panel to define a customer and their related locations (sites). Once defined, the Customer field can be applied to an asset and or a user to restrict access to other customers assets, alerts and data.

(See: Asset Configuration, Access Control Configuration).

4.8.2. Create a Customer

To create a Customer:


1. Click the “customer” icon in the menu bar at the top.
2. Click the plus icon in the bottom left corner of the customer panel.
3. Enter the name of the Customer to be added and press Enter.
4. Enter the Username and Password fields.
5. Click the Save icon to in the upper right corner.
6. Proceed to creating a Customer Site.



4.8.3. Create a Customer Site

To create a site for a Customer:


1. Click the customer to which you wish to add the site.
2. Click the plus icon in the bottom of the site panel.
3. Enter the site name and press Enter.
4. Add additional sites if applicable.
5. Click the Save icon to in the upper right corner.



4.8.4. Delete a Customer

To delete a Customer:


1. Click the check box of the customer you wish to delete.
2. Click the minus icon in the bottom of the site panel.
3. Click the Save icon to in the upper right corner.



4.8.5. Delete a Customer Site

To delete a site for a Customer:

1. Click the customer in which you wish to delete the site.
2. Click the minus icon in the bottom of the site panel.
3. Click the Save icon to in the upper right corner.



4.9. Access Control

4.9.1. Overview

The Access Controls Configuration panel allows for specific Role Based Access Controls to be enabled. These controls are based on the role of the user and the customer to which they belong.

You can select the following tabs on this page:

- *Permission Groups Tab*
- *Users Tab*
- *Nodes Tab*
- *Realms Tab*
- *Protected Subnets Tab*
- *Password Policy Tab*
- *SAML Tab*


4.9.2. Permission Groups Tab

The first tab under the Access Controls is the Permission Groups. This allows the admin to define a group that has specific capabilities/rights and subsequently add users to these groups.

Create a Permission Group

To create a Permission Group:

1. Click the Permission Group tab under the Access Control panel. A list of defined groups will be displayed.
2. Click the blue plus icon at the bottom of the panel.
3. Fill in the name of the group and select Realm Context drop-down button. This will always be local for a single Arbitrator deployment.
4. Click the Timeout box if you wish this user group to have their session timeout for non- use and require them to log back into the UI.
5. Select each system screen name tab that you wish to grant access to this group. As you select each tab it will turn green indicating that this system screen will be available to this group.
6. Click the blue check icon when complete.
7. Click Save to complete the addition of the group.



Assign and remove users to/from a permission group

Assign a User to a Permission Group

1. Click User next to the Permission tab. A list of All Users and Users in Groups will be displayed.
2. Click the Group to which you wish to add a User.
3. Drag the desired user(s) from the “All Users” section to the drop zone under “Users in Group”.
4. To remove a User from a Permission Group simply drag the user from the “Users in Group” section over to the “All Users” section
5. Click Save to complete the action.

The screenshot displays the 'ACCESS CONTROL' interface with the 'Users' tab selected. At the top, there are navigation tabs: 'Permission Groups', 'Users', 'Nodes', 'Realms', 'Protected Subnets', 'Password Policy', and 'SAML'. Below this is a table of permission groups:

Group Name	Realm Context	Timeout	
<input type="checkbox"/> Science Logic	(focal)	<input type="checkbox"/>	
<input type="checkbox"/> SuperUser	(focal)	<input type="checkbox"/>	
<input type="checkbox"/> Admin	(focal)	<input type="checkbox"/>	
<input type="checkbox"/> SiLo Test	(focal)	<input type="checkbox"/>	
<input type="checkbox"/> Guest	(focal)	<input type="checkbox"/>	
<input type="checkbox"/> Typical	(focal)	<input checked="" type="checkbox"/>	
<input type="checkbox"/> Monitor	(focal)	<input checked="" type="checkbox"/>	
<input type="checkbox"/> Test	(focal)	<input type="checkbox"/>	

Below the table, there are two tabs: 'Permissions' and 'Users'. The 'Users' tab is active, showing a 'Users in Group' section with a search box containing 'testing' and a list of users under the 'All Users' section:

- Administrator
- Alain Jansen
- Andrew Froesch
- Arda Savran
- Guest Account
- layerx
- testing2
- View Only
- Vodafone
- wstrobels

A 'Save' button is located at the bottom right. A status bar at the bottom indicates 'Changes have been made'.

4.9.3. Users Tab

The Users tab allows you to create a new user or modify an existing one. The users can be set up as “Super Users” or assigned roles in the permission groups. Once the user is added and saved then they will be available to add to the Permission Groups per the last section.

Add a new user

To create a new User:

1. Click the User tab at the top of the screen next to Permission Groups.
2. Click the blue plus icon at the bottom of the screen.
3. Fill in the required fields. (Full Name, Username, Password, Confirm and Email).
4. Check the Super-User box if applicable.
5. Check the Force Password Change if you want this user to follow the Password Policy.
6. Click the Locked Out box if you want this user to time on inactivity on the UI.
7. Select the Customer drop-down box and assign the user to a customer.
8. Check the Disable multi-tenancy if this is a single customer and multi-tenancy does not apply.
9. Click the Blue check icon to set the user.
10. Click the Save button to save the user.

The screenshot displays the 'ACCESS CONTROL' interface with the 'Users' tab selected. The table below shows existing users and their attributes:

<input type="checkbox"/>	Full Name	Username	Password	Confirm	Email	Super-User	Force Password Change	Locked Out	
<input type="checkbox"/>	Administrator	admin	*****	*****	afrosch@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	Alain Jansen	ajansen	*****	*****	ajansen@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	Andrew Frosch	afrosch	*****	*****	afrosch@layerxtech.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	Arda Savran	asavran	*****	*****	asavran@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	Guest Account	guest	*****	*****	support@layerxtech.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	layerx	layerx	*****	*****	support@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	testing	testing	*****	*****	support@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	testing2	testing2	*****	*****	support@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	View Only	viewonly	*****	*****	view@layerxtech.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	Vodafone	voda	*****	*****	support@layerxtech.com	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
<input type="checkbox"/>	wstrobelt	wstrobelt	*****	*****	wstrobelt@layerxtech.com	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>

At the bottom of the interface, there is a form for adding a new user with the following fields:

- Full Name:
- Username:
- Password:
- Confirm:
- Email:
- Customer:
- Disable multi-tenancy:

A blue plus icon is located at the bottom left, and a 'Save' button is at the bottom right. A red error bar at the bottom indicates 'Errors exist'.

Delete a user

To delete a User:

1. Click the check box next to the User name that you wish to delete.
2. Click the minus icon at the bottom of the screen.
3. Click the Save button to save your changes.


4.9.4. Nodes Tab

The Nodes tab allows you to create a new Arbitrator Correlation or Dashboard/Reporting node. Once it is added and saved then the node can be added to a Realm with other nodes.

Create a node

To create a Node:

1. Click the Node tab at the top of the screen next to Users.
2. Click the blue plus icon at the bottom of the screen.
3. Fill in the required fields. (System, GUI IP Address, Username and Password).
4. Check the either the Direct box (http) or the Secure box (https) to select the communication method.
5. Select the Appliance drop-down box and choose the type of system you are adding.
6. Click the Blue check icon to set the Node.
7. Click the Save button to save the Node.



Delete a node

To delete a Node:

1. Click the check box next to the Node name that you wish to delete.
2. Click the minus icon at the bottom of the screen.
3. Click the Save button to save your changes.


4.9.5. Realms Tab

The Realm tab allows you to create a new Realm where VOSS Insights systems can be grouped to communicate with each other. Once it is added and saved then Nodes can be added to the Realm.

Create a realm

To create a Realm:

1. Click the Realm tab at the top of the screen next to Nodes.
2. Click the blue plus icon at the bottom of the screen.
3. Fill in the Realm name that you desire.
4. Click the Blue check icon to set the Realm.
5. Drag the systems that you want in the Realm into the drop zone.
6. Click the Save button to save the Realm.



Delete a realm

To delete a Realm:

1. Click the check box next to the Realm name that you wish to delete.
2. Click the minus icon at the bottom of the screen.
3. Click the Save button to save your changes.

4.9.6. Protected Subnets Tab

The Protected Subnets tab allows you to input the IP addresses of subnets that will be protected from a control running against them. The Control will check this list prior to running and will not run a script against a device that is within a protected subnet.

Create a protected subnet


To create a Protected Subnet:

1. Click the Protected Subnet tab at the top of the screen next to Realms.
2. Click the blue plus icon at the bottom of the screen.
3. Fill in the Name, IP Address and Mask of the Protected Subnet.
4. Click the Blue check icon to set the Protected Subnet.
5. Click the Save button to save your changes.

Delete a protected subnet

To delete a Protected Subnet:

1. Click the check box next to the Protected Subnet name that you wish to delete.
2. Click the minus icon at the bottom of the screen.
3. Click the Save button to save your changes.



4.9.7. Password Policy Tab

The Password Policy tab allows you to set and enforce password rules to access the system. Each field is optional thus the user can choose the best policy to enforce.

Create a password policy

To create a Password Policy:

1. Click the Password Policy tab at the top of the screen next to Protected Subnets.
2. Within the box you have an option of Minimum Length, Minimum Uppercase, Minimum Lowercase, Minimum Numeric, Minimum Special, Password Lifespan and Maximum Login Attempts.
3. Fill in the desired inputs into each of these fields.
4. Click the Save button to save your changes.

The screenshot shows the 'ACCESS CONTROL' configuration interface. The 'Password Policy' tab is selected, displaying a form with the following settings:

Setting	Value	Character Set
Minimum Length	7	
Minimum Uppercase	1	A-Z
Minimum Lowercase	1	a-z
Minimum Numeric	1	0-9
Minimum Special	1	!@#%&*()[]
Password Lifespan	0	days
Maximum Login Attempts	20	

A 'Save' button is located at the bottom of the form.

4.9.8. SAML Tab

The SAML tab allows you to configure single sign-on (SSO) to other user management platforms via the Security Assertion Markup Language (SAML). This is an open standard for exchanging authentication and authorization data between systems.

Note: SAML is an open standard for exchanging authentication and authorization data between parties, in particular, between an identity provider and a service provider. SAML is an XML-based markup language for security assertions (statements that service providers use to make access-control decisions).

VOSS Insights supports SSO for authentication via the SAML v2.0 standard for SSO. When SAML is enabled for your system, the **Sign Out** menu option (accessible via the **admin** menu) is not required or available as the Insights system does not initiate the termination in this case.

SAML is enabled/disabled on the SAML tab of the Configuration screen in Arbitrator. To bypass SAML authentication, you can set `nosaml=true` in the URL.

Set up SSO via SAML

To create single sign-on via SAML:

1. Click the SAML tab at the top of the screen (adjacent to Password Policy). The attributes on this page require you to interact with your administrator of allowed users.
2. Click the box next to Enable SAML.

Note: The **Sign Out** option is removed from the Profile menu when SAML is enabled.

3. If the system is supporting a single customer, then click the Disable Multi-Tenancy.
4. Fill in the optional principal attributes.
5. From your administrator obtain the Identity Provider Metadata XML and paste it into the box provided.
6. From the following boxes provide each of the following to your Identity Provider:
 - a. Audience URL (SP Entity ID)
 - b. Single Login URL
 - c. Single Logout URL
 - d. Click to view or download the platform SAML Metadata
 - e. Click to view or download the platform X.509 Certificate (2048 Bit)
7. Click the Save button to commit the SAML configuration.
8. (See Figures on the next few pages.)

ACCESS CONTROL

Permission Groups Users Nodes Realms Protected Subnets Password Policy **SAML**

Enable SAML

Disable Multi Tenancy

SAML Signature Algorithm sha1

Attribute Mappings

Email (Optional):

Username (Optional):

First or Display Name (Optional):

Last Name (Optional):

Identity Provider Metadata XML

* Required

Paste your metadata XML here

Service Provider Information

Provide this information to your Identity Provider

Audience URI (SP Entity ID):

Single Login URL:

Single Logout URL:

Metadata: [View Details](#) | [Download](#)

X.509 Certificate (2048 Bit): [View Details](#) | [Download](#)

Save

ACCESS CONTROL [Permission Groups](#) [Users](#) [Nodes](#) [Realms](#) [Protected Subnets](#) [Password Policy](#) [SAML](#)

Enable SAML

Disable Multi Tenancy

SAML Signature Algorithm: sha1

Attribute Mappings

Email (Optional):

Username (Optional):

First or Display Name (Optional):

Last Name (Optional):

Identity Provider Metadata XML *** Required**

Paste your metadata XML here

SAML Metadata

```
<?xml version="1.0"?>
<md:EntityDescriptor xmlns:md="urn:oasis:names:tc:SAML:2.0:metadata"
xmlns:ds="http://www.w3.org/2000/09/xmldsig#"
entityID="http://demoarb.layerxtech.com/saml2/module.php/saml/sp/metadata.php/default-sp">
<md:SPSSODescriptor protocolSupportEnumeration="urn:oasis:names:tc:SAML:1.1:protocol"
xmlns:oasis:names:tc:SAML:2.0:protocol">
<md:KeyDescriptor use="signing">
<ds:KeyInfo xmlns:ds="http://www.w3.org/2000/09/xmldsig#">
<ds:X509Data>

<ds:X509Certificate>MIIDzCCAs+gAwIBAgLJAlyQ+0SPiFX0MA0GCSqGSIb3DQEBCwUAMIGJM0swC
QYDVQQGEwJVUzEOMAwGA1UECAwFVG4YXmxDzANBglNVBAcMBklydmliuZzEPMA0GA1UECgwwb3R5Z291Y291MIIlBjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBcGK
CAQEA4ZgbcZEgq3E/RrHvoMyyjhYtcsGITvqvuknibkmD9eP75vBS4QyIT55HY7DW72zGrjGqsjrpk5
DPBIMf6kBljIMijUbK4V3L0TCoaCq5u0rD9YLSeVAmSm0aNF/X1diTAb3Lc8VqMceh7PsvMn9CqCImJ++x
3U2BwAGS78OC6BUUhD4d8U4E5/WsJ+x1wEceYs/RGN16c7A156O6Yr9BeUj000pq6mk6xYXjC6XWNv
LTK18G5ZcG5NAUJKKdnTep4yhgtokRJuXh2wVbDrOJZFk+D7yQLSspfc41DbVmfJRCla7LgkGdqv+R
hBOKVjOpVQ5Z6w2T5xlwbdwIDAQABo1AwTAdBgNVHQ4EFgQUUvFDaBSaubH6fUtzgbEVEm8vBtlw
HwYDVROjBBgwFoAUUvFDaBSaubH6fUtzgbEVEm8vBtlwQAYDVROjBTAUwAwEB/zANBgkqhkiG9w0BA
QsFAAOCAQEAAyK084TvcTgZxuoNhcX20f9T6v7IRzO1280Uih8ydBSwbNmP9vXP69IA9dzImi4TUHfDwJq
Elz+M4HKz07DzZn60LW+ZNWZDXnodFzuYAThdsVkeZn+BXT+vD3w9fPNmxpPPFbK8e6X/8eJum63cil
8Kbd4yVS7750VDQPBT2JulV8JizjQSUr11MDiR3R9Z+EtIKUjJlt4CLVsn9h40fzDYobr315XKoleDiSq7Vy9
WEYXP00IHm6nkEvUs85jyLxsXcjw3NTbtzQeMBppuVOByGValEWlGjFyg8++t/qGJuoCQR/LT06LzFek2r
Cg/t9wGzEnmjwHYpGw==</ds:X509Certificate>
</ds:X509Data>
```

Service Provider Information

Provide this information to your Identity Provider

Audience URI (SP Ent ID):

Single Login URL:

Single Logout URL:

Metadata: [View Details](#) [Download](#)

X.509 Certificate (2048 Bit): [View Details](#) [Download](#)

Save

ACCESS CONTROL | Permission Groups | Users | Nodes | Realms | Protected Subnets | Password Policy | SAML

Enable SAML

Disable Multi Tenancy

SAML Signature Algorithm sha1

Attribute Mappings

Email (Optional):

Username (Optional):

First or Display Name (Optional):

Last Name (Optional):

SAML Certificate X

-----BEGIN CERTIFICATE-----

```

MIID5zCCAs+gAwIBAgIJAlY0+05PFX0MA0GCSqGSIb3DQEBCwUAMIGJMqwCOYD
VQQGEwJVUzEOMAwGA1UEGA1UECQwG9w0BQGF5ZXJ4MQ8wDQYDVQQLEDAZsYXl0cngE
DAOBgNVBAMMB2RidnBhcnRvTAJ
BgkqhkiG9w0BCQEFN1cHBvcnRAbG95ZXI4dGVjaC5jb20wHhcNMTE3MjM1
MzQ3WWhcNjgwMTE3MjM1MzQ3WJCBTELAAkGA1UEBhMCVWxkDjAMBgNVBAgMBVRl
eFZlMQ8wDQYDVQQGEwF5ZXJ4MQ8wDQYDVQQLEDAZsYXl0cngEFAAOCAQ8AMIIB
CgKCAQEA
4ZgbuCEgq3E/RrHvoMyyjHYtcsGiTvquvKmbkmD9eP75vBS4fQyIT55HY7DW7z
GjGqs/pk5sDPBIM8kBUIMjUbk4V3L0TCoaCq5u0rjD9YLSelVAMsm0eNF/X1
dITab3Lc9VqMceh7PsvMn9CqCImJ+xx3J2BvAGS78OC6BUUhD4d8Uf4E5WsJ+x1w
EceYsRGN16c7Ai56O6Yr9BelU000pq6mk8xYXIC6XWVnLTKi8G5zcG5NAUHKKn
Tep4yhgctkRjUbXh2wWbD/rCjZFK+D7yDLSpfc41DbVmfJRCla7LgkGdqV+RhB0
KVtjOpVQ5Z6w2T5xIwwbdwIDAQABo1AwTJAdBgNVHQ4EFgQUUvDaBSaubH6fUt
zgbEVEm8vBtlwHwYDVR0jBBgwFoAUUvDaBSaubH6fUtzgbEVEm8vBtlwDAYDVR0T
BAUwAwEB/zANBgkqhkiG9w0BAQsFAAOCAQEAAyK094TvcTgZxuoNhcX20f9T6vI7I
RzOt280Uj8ydBSwbNimP9vXP69IA9dzlml4TUHDWjQEtz+M/4HKz07Dz2h60LW+Z
NWZ0XnodxFzYATrdsVKEZn+BXT+vD3w8fPNmxxPPfBkBe6X/8eJum63cll8Kbd4
yVS7750VDQPBT2JuuV8JzjJQSUR1MDlr3R9Z+EtIKUjlt4CLVsn8h40tzDYo
br315XkoJeDISq7Vy9WEYXP00IHm6nkEvUs95jyLxsXcjw3NTbtzQeMBppuV0By
GValEWigFyg8++/qGJuoCQn/LT06LzFek2rCg/9wGzEnmjnwHYpGw==
-----END CERTIFICATE-----
            
```

Identity Provider Metadata XML

* Required

Poste your metadata XML here

Service Provider Information

Provide this information to your Identity Provider

Audience URI (SP Entity ID):

Single Login URL:

Single Logout URL:

Metadata: [View Details](#) [Download](#)

X.509 Certificate (2048 Bit): [View Details](#) [Download](#)

Save

4.10. Import & Export


4.10.1. Overview

The Import & Export Configuration panel allows you to select all or parts of the system configuration to be exported to file or to import already exported files into the system.

4.10.2. Exporting

To export configuration items:


1. Click the Export tab at the top of the screen.
2. On the left-hand side will be folders containing all of the configuration items. Either drag whole folders over to the drop zone or open a folder and select a specific item to drag to the drop zone.
3. Once complete give the package a name in the box next to Package Name.
4. Then give the package a description in the box next to Package Description.
5. When complete click the Export button.
6. The package file will download to your local computer.



4.10.3. Importing

To import configuration items:

1. Click the Import tab at the top of the screen.
2. Select the file you wish to import by clicking the “choose file” button. This will open up your local file system to select the file from where you have it stored on your computer.
3. Double click the file or highlight it and click “Open”.
4. Click the Upload button. This will open up all of the configuration items you are importing.
5. Make any changes to the settings as required.
6. Click Import.
7. A progress screen will pop up. Once complete click OK.



4.11. Archive Management

4.11.1. Overview

The Archive Management system configuration page provides options on backing up and configuring the Arbitrator correlation platform.

You can select the following tabs on this page:

- [Configuration Management Tab](#)
- [Log Management Tab](#)

4.11.2. Configuration Management Tab

You can select the following tabs on the Archive Management > Configuration Management tab:


- [API Config Tab](#)
- [Archive Tab](#)
- [Cisco SDL Tab](#)
- [Collect Tab](#)
- [Data User Tab](#)
- [Import Tab](#)
- [LDAP Tab](#)
- [License Tab](#)
- [Probe Tab](#)
- [Proxy Tab](#)
- [SNMP Tab](#)
- [Syslog Tab](#)
- [Tunnel Tab](#)

API Config Tab

This tab allows you to set up a number of API configurations to enable monitoring, for example, of Webex or MS Teams.

Webex Config

The Webex Config option allows the configuration of Webex monitoring. A dashboard is available to visualize the data.



Note: For Webex API support, your network should be configured to access: <https://webexapis.com/v1>, port 443. (Admin menu > LayerX Network Configuration, **DNS Settings** may need to be configured to reach the external site.)

To configure Webex API:

1. From the Arbitrator main user interface, click the **System Configuration** toolbar icon (wrench) to open the Arbitrator **Configuration** GUI.
2. Click the toolbar **Cabinet** icon to open **Archive Management**.
3. On the **Configuration Management** tab, select the **API Config** tab. 3. On the **API Config** tab, select **Webex Config**, then configure settings in the right pane:
 - a. Click the **Create Access Token** button, then fill out your account credentials and copy the JSON string that performs OAuth handshake with Webex. You'll paste this into **AccessToken**.
 - b. At the **Enabled** drop-down, select enabled.
 - c. At **CUSTOMER**, fill out the customer name (if multi-tenancy is required).
 - d. At **AccessToken**, paste the copied JSON token from step a.

The JSON format is as follows (line breaks here not in string):

```

{"access_token":"xxxxxxxxxxxxxxxxxxxxxxxxxxxx",
 "expires_in":nnnnnn,
 "refresh_token":"xxxxxxxxxxxxxxxxxxxxxxxx",
 "refresh_token_expires_in":nnnnnn,
 "token_type":"Bearer"}

```

- e. Click **Verify Access Token** and to verify, inspect the output in **View Output**.
- f. Click **Save Access Token**, which will create a new Customer-specific “Webex Config - <XYZ>” entry, under the **API Config** list. (You need to click away and return to **Configuration Management** to reload with the new entry.)

The screenshot displays the Voss Archive Management web interface. The top navigation bar includes the Voss logo, a series of icons, and the text "Days remaining: Unlimited". Below this, the main navigation area shows "ARCHIVE MANAGEMENT" with sub-tabs for "Configuration Management" and "Log Management". A secondary navigation bar lists various configuration categories: "API Config", "Archive", "Blue Jeans Config", "Cisco SDL", "Collect", "Import", "LDAP", "Probe", "SNMP", "Syslog", and "Tunnel".

The main content area is titled "Creation" and lists several configuration items: "DEM Config", "Webex Config" (which is selected and highlighted in blue), and "Zoom Config". A yellow notification banner at the top of the main content area states "Changes have been made to this configuration item".

The "Webex Config" configuration page is shown. It includes a description: "Allows the enable and configuration of Webex monitoring." Below this is a "Create Access Token" section with a "Create Access Token" button and a note: "This step is required to allow the creation of an access token." The "Enabled" section has a dropdown menu set to "enabled" and a note: "Capture Webex's statistics using the Access Token provided from https://marketplace.webex.us/ Recommendation: Manually overwrite the ExpirationTime to a much greater time." The "CUSTOMER" section has a text input field containing "ABC Telecom" and a note: "Name of Customer." The "AccessToken" section has a text input field containing a JSON object: {"access_token": "ZjlyZjAyYmEiYTYyNS00YWZlLWlzOGEt"} and a note: "AccessToken to be used for requests."

On the right side of the configuration page, there is a "Command" panel showing the executed command: "Webex Config: Create Access Token". The status is "Finished" and the output is "success". Below this panel are "Close" and "View Output" buttons.


Created configurations can be deleted or modified. This will be needed for Access Tokens, as these contain an `expires_in` value.

MS Teams Config


MS Teams Config settings allow you to configure MS Teams monitoring.

The MS Teams API configuration requires an initial application registration on Microsoft Azure. To set this up:

1. Search for Azure Active Directory:



2. Select **Manage > App registrations**, then select **New Registration**



3. Fill out a meaningful application **Name** to display to users and under **Supported account types**, select **Accounts in this organization directory** and click **Register**.

Microsoft Azure

Home > VOSS Solutions | App registrations >

Register an application ...

*** Name**

The user-facing display name for this application (this can be changed later).

Voss-cloud-collector

Supported account types

Who can use this application or access this API?

Accounts in this organizational directory only (VOSS Solutions only - Single tenant)

Accounts in any organizational directory (Any Azure AD directory - Multitenant)

Accounts in any organizational directory (Any Azure AD directory - Multitenant) and personal Microsoft acc

Personal Microsoft accounts only

4. When the new application is registered, locate the **Application (client) ID** and **Directory (tenant) ID** on the next page and store these values in a secure location.


The screenshot displays the Microsoft Azure portal interface for an application named "VOSS MS Teams Collector". The left-hand navigation pane includes sections for "Manage" and "API permissions", with the latter being highlighted by a red box. The main content area shows the "Essentials" section, where the "Application (client) ID" and "Directory (tenant) ID" fields are redacted with black bars and also highlighted by red boxes. The "Supported account types" is set to "My organization".

5. Select the **API permissions** menu under **Manage** and then select the following **Application permissions**:


- CallRecords.Read.All
- Device.Read.All
- DeviceManagementApps.Read.All
- DeviceManagementApps.ReadWrite.All
- DeviceManagementConfiguration.Read.All
- DeviceManagementConfiguration.ReadWrite.All
- DeviceManagementServiceConfig.Read.All
- DeviceManagementServiceConfig.ReadWrite.All
- Directory.Read.All
- Directory.ReadWrite.All
- User.Read.All
- User.ReadBasic.All

- User.ReadWrite.All
- Group.Read.All
- Group.ReadWrite.All
- GroupMember.Read.All
- ServiceHealth.Read.All
- TeamworkDevice.Read.All
- TeamworkDevice.ReadWrite.All

6. Grant admin consent:



7. From **Certificates & secrets**, create authentication from **New client secret**:



8. Copy the value and store in a secure location.

Description	Expires	Value ⓘ	Secret ID	
VOSS MS Teams Collector Secret	6/22/2023	[REDACTED]	[REDACTED]	 

The following stored values will be used on the Arbitrator configuration dialog screen:

- Application (client) ID
- Client secret value
- Directory (tenant) ID

Configure the tenant collection from the Arbitrator

Configuration is carried out on the Arbitrator **Settings** menu via **Archive Management > API Config > MS Teams Config**.

The screenshot displays the Voss Archive Management web interface. The top navigation bar includes the Voss logo and various system icons. Below the navigation bar, the 'ARCHIVE MANAGEMENT' section is active, with sub-tabs for 'Configuration Management' and 'Log Management'. A secondary navigation bar lists various configuration options: 'API Config', 'Archive', 'Blue Jeans Config', 'Cisco SDL', 'Collect', 'Import', 'LDAP', 'Probe', 'SNMP', 'Syslog', and 'Tunnel'. On the left, a sidebar menu shows 'Creation', 'DEM Config', 'MS Teams Config' (highlighted), 'Webex Config', and 'Zoom Config'. The main content area is titled 'MS Teams Config' and includes a yellow notification banner stating 'Changes have been made to this configuration'. The form contains several input fields: 'Name' (with a hint 'Friendly user name of Customer'), 'ClientID' (with a hint 'Client ID to be used for requests'), 'ClientSecret' (with a hint 'Client Secret to be used for requests'), and 'CUSTOMER' (with a hint 'Tenant id of Customer'). There is an 'Enabled' checkbox set to 'enabled'. Below the form, there are two buttons: 'Save Data' and 'Verify Access'. The 'Save Data' button has a hint 'Create an entry for the supplied customer.' The 'Verify Access' button has a hint 'Tests the API access by trying to fetch the license info. Response should be JSON-formatted list of license values, or else MS Graph error codes.'

New Tenants can be created with **Enabled** either enabled or disabled. If disabled, no API requests will be made until it is enabled.

1. Enter stored values:

- Enter the tenant id (**Directory (tenant) ID**) in the **CUSTOMER** field
- Enter an easily identifiable account name in the **Name** field.
- Enter the client ID (**Application (client) ID**) in the **ClientID** field.
- Enter the client secret **Value** in the **ClientSecret** field.


These values should be for a client that is dedicated to this use and should not be used to request a token from any other source while the API collector is enabled.

2. Click **Save Data** to save the configuration.

3. Refresh the screen (move away from the configuration screen to another and back) to see the new configuration.

Zoom Config

An access token is required for the configuration of Zoom monitoring.



Click the **Create Access Token** button to be redirected to get an access token.

1. If Zoom statistics are to be captured, select **enabled** from the **Enabled** drop-down.
2. Enter a **Customer** name for the associated customer.
3. Enter the received access token in the **AccessToken** input box.
4. Enter a refresh token in the **RefreshToken** input box.
5. Click the **Verify Access Token** button to test the entered access token.


Archive Tab

The Archive tab provides a number of options based on the specific functions you wish to backup.

Setup

The system does a backup daily. For the most part, there is nothing for the user to configure. All data and configurations that exists on the system are archived automatically on a daily basis.

Archived data are logically grouped together and by default stored into separate archived files locally on the box. There is a separate page for each Archive group. More detailed information about each Archive group can be found on the individual Archive group pages. The user also has the option to mount an NFS drive to the system. All archived files will then get archived to the NFS mounted drive. Note: removing the NFS mount will NOT copy the NFS contents back to local storage. Only NFS v3 mounts are currently supported today.




Arbitrator Backup

This page contains the settings for the backup of the Arbitrator. There is nothing to edit here. The settings are simply displayed for informational purposes only. This Archive group contains the following data: Arbitrator Configuration settings (Database: Assets, Alerts, Policies, Rules, Probe Groups, Response Procedures, Controls), User Permissions settings

(Idap), NDX files, Avaya data, Pexip data, and all other data currently being collected in the Arbitrator database.

The backup excludes data from the CALL table, Cisco Tables, and raw Cisco CDR/CMR files. Data in the CALL table can be very large and is expendable. Cisco Tables and raw Cisco CDR/CMR files are part of a separate Archive group.




Cisco Files

Archival for Cisco files. This Archive group will back up all Cisco CDR and Cisco CMR raw files. These are the files that are SFTP'd to the system by the Cisco Call Manager. The settings here are for informational purposes only. However, the user may disable the storage of raw Cisco CDR and Cisco CMR raw files on the system. This option could be used to conserve disk space.

The screenshot shows the 'ARCHIVE MANAGEMENT' web interface. At the top, there are tabs for 'Configuration Management' and 'Log Management'. Below these are navigation buttons for 'Archive', 'Collect', 'LDAP', 'SNMP', 'Syslog', and 'Tunnel'. A 'Save' button is located in the top right corner. On the left side, there is a sidebar menu with options: 'Setup', 'Arbitrator Backup', 'Cisco Files' (which is highlighted in blue), 'Cisco SQL', 'Pcap Files', and 'Remote Storage'. The main content area has a yellow notification bar that says 'Changes have been made to this configuration item.' Below this is the 'Cisco Files' configuration section. It includes a description: 'Archival for Cisco files. This Archive group will backup all Cisco CDR and Cisco CMR raw files. These are the files that are shipped to the system by the Cisco Call Manager. The settings here are for informational purposes only. However, the user may disable the storage of raw Cisco CDR and Cisco CMR raw files on the system. This option could be used to conserve disk space.' The configuration fields are: 'status' (dropdown menu set to 'enabled'), 'archive_interval' (dropdown menu set to 'daily'), 'method' (dropdown menu set to 'local'), 'destination' (text input field containing '/chroot/scp/pub/ft_archive'), and 'monthsKept' (dropdown menu set to 'notSupported').

Cisco SQL

Archival for Cisco SQL data. This Archive group will back up all Cisco data in the database tables. This is the data that has already been processed by the system. There is nothing to edit here. The settings here are for information purposes only. The data here is grouped together by the Cisco Call Manager IP Address. This allows for more granular control on which Call Manager data to import.



Ndx

This Archive group will manage Ndx files on the system. Default **monthsKept** is 6 months.

Ndx

This screen can be used to manage Ndx files on the system.

max_ndx_file_size

1

The maximum size the ndx searchable file should be. Once the max size is hit, the ndx server will create a new ndx file.

max_searchable_days

1

The maximum number of days that should be searchable. Ndx files greater than this time will still live on the system but will not be searchable from the UI.

monthsKept

6

The maximum number of months to keep ndx archives around. Each archived ndx will take up disk space. Warning, increasing this number too large may require customer to also increase the hard disk size.

Pexip Files

Archival for Pexip files. The system can be used to collect PEXIP data. The raw PEXIP data files are kept, by default, for historical purposes. However, in order to conserve disk space, the user may choose to disable the local storage of the raw PEXIP files.

The screenshot shows the 'ARCHIVE MANAGEMENT' interface with a navigation menu (Archive, Collect, LDAP, SNMP, Syslog, Tunnel) and a 'Save' button. A sidebar on the left lists configuration items: Setup, Arbitrator Backup, Cisco Files, Cisco SQL, Pexip Files (selected), and Remote Storage. A yellow notification bar states 'Changes have been made to this configuration item'. The main content area is titled 'Pexip Files' and contains the following configuration fields:

- status:** A dropdown menu set to 'enabled'. Below it, text explains: 'enabled' - keep original pexip files, 'disabled' - remove original pexip files. This 'disabled' option should be used to conserve disk space. The 'disabled' option will cause all pexip files to be removed. This is a permanent change.
- archive_interval:** A dropdown menu set to 'daily'.
- method:** A dropdown menu set to 'local'.
- destination:** A text input field containing '/chroot/scp/pub/txt_archive'.
- monthsKept:** A text input field containing 'notSupported'.

Remote Storage

If standard / local storage is chosen in the Archive Setup page, then this screen allows the user to configure remote archival of the Arbitrator backup files. Each Archive group produces one or many archive files. The system can be configured to SCP these archive files to a backup location or to another Arbitrator.

The archives can be sent to a separate backup location (NFS, SFTP-server, SCP or remote synced to another Arbitrator).

- **archive_interval**

This can be set on a schedule of:

- i. Daily
- ii. Weekly
- iii. Monthly

- **Method: Select an option**

- **disable** - System will reset storage options, e.g. archives locations are reset to the local system if these were previously on a remote host.

- **nfs** - System will mount the filesystem as a local drive. The system drop/lxt_archive directory is linked with a symbolic link to /mnt/nfsshare on a host, thereby saving space on the system.

Selecting this option enables additional controls:

Check NFS Host

Check NFS Host

Check NFS Mount

Check NFS Mount

- * **Check NFS Host:** Click and use the **View Output** button to see verification output.
 - * **Check NFS Mount:** Check the **destination** location (entered below) *after* saving the configuration. **View Output** shows disk usage on the destination of the NFS host.
- **rsync** - System will sync the archive directory to remote system. The remote system must have rsync installed for this to work.
 - **rsyncToArb** - System will sync the archives directory to a remote Arbitrator. This utilizes the rsync protocol so both Arbitrators will always be in sync.
 - **scp** - System will copy archives to a remote location. Scp is not a sync. To reduce load on system and network, system only copies new / changing archives over to the scp location.
 - **sftp** - System will copy archives to a remote location. Sftp is not a sync. To reduce load on system and network, system only copies new / changing archives over to the sftp location.
- **IP location**
IP address. Also add **username** and **password**.
 - **destination**
The path on the remote server to the folder where backups are to be stored.

ARCHIVE MANAGEMENT
Configuration Management
Log Management

API Config
Archive
Blue Jeans Config
Cisco SDL
Collect
Import
LDAP
Probe
SNMP
Syslog
Tunnel

Save
Delete

Remote Storage

- Arbitrator Backup
- Avaya SQL
- Cisco Files
- Cisco SQL
- Cisco Expressway SQL
- Cisco RTMT SQL
- Ndx
- Pexip Files
- Pexip SQL
- Webex SQL
- UHE SQL
- Vdf Cisco
- Vdf Gspip

Changes have been made to this configuration item

Remote Storage

This page does not describe an Archive Group. If standard / local storage is chosen in the Archive Setup page, then this screen allows the user to configure remote archival of the Arbitrator backup files. Each Archive group produces one or many archive files. The system can be configured to scp these archive files to a backup location or to another Arbitrator.

archive_interval

Select an option

disabled
 nfs
 rsync
 rsyncToArb
 scp
 sftp

'disabled' - keep archives locally, 'nfs' - Will mount a network file system as a local drive, which preserves local device disk space, 'scp' - System will copy archives to a remote location. Scp is not a sync. In order to reduce load on system and network, system only copies new / changing archives over to the scp location, 'sftp' - System will copy archives to a remote location. Sftp is not a sync. In order to reduce load on system and network, system only copies new / changing archives over to the sftp location, 'rsync' - System will sync archive directory to remote system. The remote system must have rsync installed for this to work, 'rsyncToArb' - System will sync archives directory to a remote Arbitrator. This utilizes the rsync protocol so both Arbitrators will always be in sync

IP location

username

password

destination

monthsKept

See also: [Backup and Restore the Arbitrator](#).

Collect Tab

The Collect tab defines configuration options for the collection of CDRs.

Control

This panel enables and disables the processing of various file types. When a file type is disabled, files of this type are added to a backlog, and are processed when processing is re-enabled.

The table lists the control options you can enable and disable:

DEM	<p>Enables/disables Digital Experience Monitoring (DEM) collection on the Arbitrator. DEM provides the ability to test connectivity to web-based systems, such as Microsoft Teams, and to deliver metrics for the following:</p> <ul style="list-style-type: none"> • Overall round-trip times to the application • The number of hops taken • Best and worst latency • The connection path, displayed hop-by-hop <p>DEM agents on the Arbitrator provide connectivity and performance statistics to various MS Teams internet endpoints, including Microsoft Graph. When enabled, the job runs every 5 minutes, and policies (rules) imported to Arbitrator fire incident alerts when any of the DEM-collected metrics are out of the permitted thresholds. To verify that the Arbitrator policies are firing alerts and to view the logs, you can search in Arbitrator for either “dem_connectivity” or “dem_web_performance”.</p>
Cisco UCM	
Oracle SBC	
Pexip	
NGIN	Enables/disables NGIN-XML processing
Palladion	
NMR	
Infovista GSIP	
Infovista IPSLA	

The screenshot displays the Voss Archive Management Configuration Management interface. The top navigation bar includes 'ARCHIVE MANAGEMENT', 'Configuration Management', and 'Log Management'. Below this, a secondary navigation bar lists various configuration categories: API Config, Archive, Cisco SDL, **Collect**, Data User, Import, LDAP, License, Probe, Proxy, SNMP, Syslog, and Tunnel. On the right side of this bar are 'Save' and 'Delete' buttons.

The main content area is divided into two sections. On the left is a sidebar menu with the following items: **Control**, Avaya Datastore, Cisco, Cisco Remote Copy, Oracle Microsoft Operator Connect, Vdf, and Voss Analytics. The 'Control' item is highlighted.

The right section features a yellow notification banner stating 'Changes have been made to this configuration item'. Below this is the 'Control' configuration panel, which includes the following text: 'This screen allows the file processing mechanism to be suspended. The system will still receive files, but the file contents will not be processed until re-enabled.' The panel contains five toggle switches, each with a dropdown menu and a descriptive label:

- DEM**: Set to 'disabled'. Label: 'Enable/Disable Digital Experience Monitoring processing.'
- Cisco UCM**: Set to 'enabled'. Label: 'Enable/Disable Cisco Unified Call Manager processing.'
- Cisco ME**: Set to 'enabled'. Label: 'Enable/Disable Cisco ME processing.'
- Oracle SBC**: Set to 'enabled'. Label: 'Enable/Disable Oracle Session Border Controller processing.'
- Pexip**: Set to 'enabled'. Label: 'Enable/Disable Pexip processing.'

Cisco Remote Copy

This panel defines the storage location of collected Cisco CDR/CMR files.

The default location is "local", which is the local Arbitrator Correlation platform. Choose "remote arbitrator" and the processed Cisco CDR/CMR files will be stored to the database of a remote arbitrator. This is useful if the data of multiple arbitrators needs to be stored to a centralized arbitrator. The "remote_ip" needs to be filled in with the IP address of the "remote arbitrator", if configured.

The screenshot displays the Voss Archive Management web interface. The top navigation bar includes the Voss logo and several icons. Below it, the main menu shows 'ARCHIVE MANAGEMENT' with sub-menus for 'Configuration Management' and 'Log Management'. A secondary menu lists various configuration options: 'API Config', 'Archive', 'Blue Jeans Config', 'Cisco SDL', 'Collect', 'Import', 'LDAP', 'Probe', and 'SNMP'. The 'Collect' option is currently selected. On the right side of the main menu, there are 'Save' and 'Delete' buttons.

The left sidebar contains a list of configuration categories: 'Avaya Datastore', 'Cisco', 'Cisco Remote Copy' (highlighted in blue), 'Oracle Microsoft Operator Connect', 'Vdf', and 'Voss Analytics'.

The main content area shows a yellow notification banner: 'Changes have been made to this configuration item'. Below this is the 'Cisco Remote Copy' configuration form. The form title is 'Cisco Remote Copy' and the description is 'Use this to configure CDR/CMR forwarding to a remote system.' The form contains four input fields with labels and instructions:

- IP location:** The input field contains '10.13.37.8'. Below it, the instruction reads: 'Specify the IP address of the remote location.'
- username:** The input field contains 'drop'. Below it, the instruction reads: 'Specify the username to be used to access the remote location.'
- password:** The input field contains a series of dots. Below it, the instruction reads: 'Specify the password to be used to access the remote location.'
- destination:** The input field contains '/chroot/scp/pub/cucm'. Below it, the instruction reads: 'Specify the path on the remote system.'

At the bottom of the form, there is a 'Verify Config' button.

Oracle Microsoft Operator Connect

If customer CDR folders for Oracle Call Manager were set up during Arbitrator setup, then parsing CDRs and using API calls to create the call record in the MS Tenant via the Operator Connect API is configured from the setup up on the **Oracle Microsoft Operator Connect** screen.

The screenshot shows the Voss Archive Management web interface. At the top, there is a dark blue navigation bar with the Voss logo and several icons. Below this is a light blue header with the text "ARCHIVE MANAGEMENT" and "Configuration Management" (which is highlighted). To the right of "Configuration Management" is "Log Management". Below the header is a secondary navigation bar with tabs: "API Config", "Archive", "Blue Jeans Config", "Cisco SDL", "Collect" (highlighted), "Import", "LDAP", "Probe", "SNMP", "Syslog", and "Tun".

On the left side, there is a sidebar menu with the following items: "Avaya Datastore", "Cisco", "Cisco Remote Copy", "Oracle Microsoft Operator Connect" (highlighted in blue), "Vdf", and "Voss Analytics".

The main content area on the right has a yellow notification banner at the top that says "Changes have been made to this configuration item". Below this is the configuration page for "Oracle Microsoft Operator Connect". The page title is "Oracle Microsoft Operator Connect" and the description is "Use this to configure SBC forwarding to Microsoft Operator Connect." There are four input fields: "Client ID" (with a note: "Specify the client_id to be used to access the remote location."), "Client Secret" (with a note: "Specify the client_secret to be used to access the remote location."), "Tenant" (with a note: "Specify the tenant to be used to access the remote location."), and "Resource".

For CDR folder setup, see the "Add Customer CDR Folders" topic in the Arbitrator Install Guide.

Import Tab

This tab allows you to import configuration data to a server from a csv file.

Note: Only csv file imports are supported.

LDAP Tab

The system uses a local LDAP server to store user information. The system also supports authenticating with an external Microsoft Active Directory server. If an external Microsoft AD is used, the system will automatically sync all users locally. Local user accounts are necessary to set specific system privileges. Note that Microsoft AD passwords are never stored locally. Authentication always occurs with external Microsoft AD. Once authenticated, the system allows the user access based on the user's local system privileges. In order to properly configure this screen, the customer administrator must have an in-depth knowledge of the customer's Microsoft AD architecture. Improper configuration may cause too little or too many users in the system.

The screenshot shows the 'LDAP Configuration' page in the 'ARCHIVE MANAGEMENT' system. The page is divided into several sections:

- General Config:** Contains a paragraph explaining the system's use of LDAP and a 'Test LDAP Configuration' button.
- LDAP Configuration:** Includes a 'Test LDAP Configuration' button and a section for 'General LDAP Configuration' with a 'Test LDAP Configuration' button.
- Microsoft AD Configuration:** Contains multiple sections for configuring Microsoft AD, each with a 'Test LDAP Configuration' button and a 'Test LDAP Configuration' button.

The page also features a navigation bar at the top with 'ARCHIVE MANAGEMENT' and 'LDAP Configuration' tabs, and a sidebar on the left with 'LDAP Configuration' selected.

License Tab

This tab registers your system for integration with the VOSS Cloud License service for user license count auditing, and allows the licensed user counts files to be sent to VOSS automatically.

You can also view and download license files on this tab, and upload license files to VOSS.

The screenshot shows the VOSS ARCHIVE MANAGEMENT interface. The top navigation bar includes 'ARCHIVE MANAGEMENT', 'Configuration Management', and 'Log Management'. Below this, a secondary navigation bar lists various configuration options: 'API Config', 'Archive', 'Cisco SDL', 'Collect', 'Data User', 'Import', 'LDAP', 'License' (highlighted), 'Probe', 'Proxy', 'SNMP', 'Syslog', and 'Tunnel'. A 'Save' and 'Delete' button is located in the top right corner of the configuration area.

The main content area is titled 'License' and contains the following information:

- License**: This screen manages licensing with VOSS. This screen may be used to enable the periodic license delivery to VOSS. If applicable, please update firewall policies to allow interaction with platform.voss-solutions.com. Additionally, please configure proxy settings for external connectivity, if necessary.
- enabled**: A dropdown menu currently set to 'false'. Below it is the text: 'Opt-in/Enable the automatic sharing of the license file.'
- organization id**: A text input field containing 'adsf'. Below it is the text: 'The VOSS organization id associated with this device.'
- environment type**: A dropdown menu currently set to 'production'. Below it is the text: 'The VOSS account id (organisation id) associated with this device.'
- description**: A text input field containing 'A description'. Below it is the text: 'A description of this device.'
- Fetch License File**: A button labeled 'Fetch License File'.

At the bottom left of the interface, there is a 'Running command' button.

Related Topics

- [License Auditing](#)

Proxy Tab

To allow for cloud services access, proxy configuration (both authenticated and unauthenticated) is supported.

You can configure the Proxy on the Arbitrator **Settings** menu from **ARCHIVE MANAGEMENT > Configuration Management > Proxy**.

The screenshot shows the Voss Archive Management web interface. At the top, there is a dark blue navigation bar with the Voss logo and various icons. Below this is a light grey breadcrumb trail: ARCHIVE MANAGEMENT > Configuration Management > Log Management. A secondary navigation bar contains links for API Config, Archive, Blue Jeans Config, Cisco SDL, Collect, Import, LDAP, Probe, Proxy (highlighted with a red box), SNMP, Syslog, and Tunnel. On the right side of this bar are Save and Delete buttons. A yellow notification banner at the top of the main content area states: "Changes have been made to this configuration item". The main content area is titled "Proxy Config" and includes a description: "Adds configuration for Proxy use in external data creation." It contains four input fields: "ipAddress" (10.0.0.1), "proxyPort" (19001), "userName" (UserX), and "password" (masked with dots). Below these fields are two buttons: "Set Proxy" and "Remove Proxy", each with a descriptive note.

Proxy Config

Adds configuration for Proxy use in external data creation.

ipAddress
10.0.0.1
IP Address of the proxy server.

proxyPort
19001
Port of the proxy server.

userName
UserX
User for the proxy account for external access.

password
.....
Password for the proxy user account for external access.

Set Proxy
Set Proxy
Set the proxy with the settings above. (Values must be saved first.)

Remove Proxy
Remove Proxy
Clear the proxy config removing any previously configured proxy.

1. Fill out the required **Proxy Config** values: **ipAddress**, **proxyPort**, **userName** **password**.
2. Click **Save**.
3. To enable the saved values, click **Set Proxy**.

Important: The proxy is used only by services that use APIs for their data, and are set up in **Archive Management > Configuration Management > API Config:** Webex, Teams and Zoom.

If it is necessary to remove the proxy configuration, click **Remove Proxy**. This will reset the configuration to empty settings from the system. In order to clear the configuration screen, you will then need to click **Delete** at the top of the form. This will remove any confusion as to the proxy settings in the future.

SNMP Tab

This tab configures SNMP v3 user config, which allows the system to be configured to work with SNMP v3. It allows you to select the specific authentication and encryption methods to be used.

The screenshot shows the 'SNMPv3 User Config' configuration page within the 'ARCHIVE MANAGEMENT' system. The page is part of the 'Configuration Management' section, with sub-tabs for 'Archive', 'Collect', 'LDAP', 'SNMP', 'Syslog', and 'Tunnel'. A 'Save' button is visible in the top right corner. A yellow notification banner at the top states 'Changes have been made to this configuration item'. The main configuration area is titled 'SNMPv3 User Config' and includes the instruction 'Setup the configuration for SNMP.' Below this, there is a 'Commit SNMPv3 User Configuration' button. The form contains several input fields: 'Engine ID' (OCTECT STRING), 'User Name' (OCTECT STRING), 'Authentication Protocol' (dropdown menu set to 'MD5'), 'Authentication Pass Phrase' (text input), 'Encryption Protocol' (dropdown menu set to 'AES'), and 'Encryption Pass Phrase' (text input).

Syslog Tab

This tab configures the IP address of your central syslog server.

Note: This is a system-wide setting.

The system can send out syslog messages about several of the internal functions, including backup and archival success. If an IP address is specified, the system will send any internal VOSS Insights messages onto the specified syslog server.

Only one central syslog server can be specified at this time. Please validate firewall settings are open to allow incoming messages on the specified IP address and port.

The screenshot shows the 'Syslog Server' configuration page within the 'ARCHIVE MANAGEMENT' interface. The page title is 'Syslog Server' and it includes a 'Save' button. A yellow notification banner at the top states 'Changes have been made to this configuration item'. The main content area is titled 'Syslog Server' and contains the following text: 'Use this screen to configure the ip address of your central syslog server. This is a system wide setting. If an ip address is specified the system will send any internal Layer X messages onto the specified syslog server. Only one central syslog server can be specified at this time. Please validate firewall settings are open to allow incoming messages on the specified ip address and port.' Below this text are three input fields: 'external_syslog_ip' (with a text input field), 'protocol' (with a dropdown menu set to 'tcp'), and 'external_syslog_port' (with a text input field set to '514'). Each input field has a small 'Optional' label and a note: 'Optional. Enter in the ip address of your organization's central syslog server. A single Ip Address or a single Domain name. Note. Domain name entries must resolve through the system configured DNS (asn specified in system DNS settings)' for the IP field, and 'Optional. Enter in the port. Default syslog port is 514' for the port field.

Tunnel Tab

This tab allows you to create VPN tunnels between Arbitrator platforms. Three options are available:

- Creation - allows creation of SSH tunnel to the specified endpoint, including the interim hops needed.

ARCHIVE MANAGEMENT Configuration Management Log Management

Archive Collect LDAP SNMP Syslog **Tunnel**

Save

Changes have been made to this configuration item

Creation

Allows the creation of SSH tunnel to the specified endpoint, including interim hops needed.

Create Tunnel

Create Tunnel

Create a tunnel to the requested device, and optional port.

remoteAddress
172.30.11.100

remotePort
3088

InterimDevice
169.254.5.12

Fetch InterimDevices

Fetch InterimDevices List

Fetch a list of possible interim devices. This is required when the Arbitrator is connected to multiple VPNs, and the IP address specified in the 'remoteAddress' field is reused within the different VPNs.

- Management - used for listing and managing all of the existing tunnels.

ARCHIVE MANAGEMENT Configuration Management Log Management

Archive Collect LDAP SNMP Syslog **Tunnel**

Save

Changes have been made to this configuration item

Management

Allows the listing, and management of existing tunnels.

List Active Tunnels

List Active Tunnels

List only active tunnels.


Remove Specified Tunnel

Remove and close the tunnel specified

Close the active tunnel, by requestid.

requestid

- Request History - allows listing of tunnel requests and management of those requests.



4.11.3. Log Management Tab

The **Log Management** tab (in **Archive Management**) allows you to customize the archival of the index data store. It can be performed based on Size, Time or a combination of both.

Set the archival process

This procedure sets up the archival process.

1. Click on the Log Management tab.
2. Select the file size at which to start the archive.
3. Select the time interval at which to start the archive.
4. Add the location to where the archive file will be sent.
5. Set the **IP Address**, Choose the **Method** of transport (e.g. SFTP), give it a **Path** and input any **Credentials** required.


Archive Methods

<input type="checkbox"/> IP Address	Method
0.0.0.0	SCP
	SCP
	SFTP
	SMP

ARCHIVE MANAGEMENT Configuration Management: Log Management

Errors exist Save

Archive Settings


 Current Intervals
 4 GB
 10 Days
 Last Archive Time
 Aug 19, 2018 13:50

Archive Index Every
 4 GB
 10 Days

Alerting Options
 Alert on archive success
 Alert on archive failure

Archive Methods

<input type="checkbox"/> IP Address	Method	Path	Credentials
0.0.0.0	SCP		None

4.12. Tools


4.12.1. Overview

The **SNMP Tools** page allows you to load or import MIBs and then build SNMP actions/ scripts to be saved as probes within the platform.


Insights ships with a library of MIBs that can be opened by choosing the **Load MIB** button. If a new one is needed it can be imported by selecting the **Import MIBs** button.

4.12.2. Load a MIB


1. On the **Tools** page, click **Load MIB**.
2. In the **Select a MIB** dialog, view the choice of all the manufacturer MIBs available in the system, then select the relevant MIB.
3. Scroll through and select the desired MIB.



3. Once selected you can open up all of the branches and leaves and view each associated OID.
4. Choose the folder you wish to use, and fill out the connection settings for that system.
5. Select the Connection button, input the host name or IP and choose the SNMP version. If selecting V3 then a set of different parameters will pop up and you will need to fill these in.



6. Choose the operation to perform: GET, GET NEXT or WALK
7. The operation will return the values of the OID you query in the field below it. Checking any of the boxes beside the field will un-gray the “Create Probe” box.
8. Do this for each Probe you want to create.



The screenshot shows the 'OID' management interface. At the top, the 'OID' field contains '1.3.6.1.4.1.6876.1'. To its right is an 'Operation' dropdown menu with options: 'Get' (checked), 'Get Next', and 'Walk'. A 'Run' button is located to the right of the dropdown. Below this is the 'Results' section, which includes a search bar for 'Text OID', a 'Toggle Numeric/Text OID' button, and a 'Create Probe' button. The main results table is as follows:

Text OID	Value	Type
<input checked="" type="checkbox"/> VMWARE-SYSTEM-MIB::vmwProdName.0	VMware ESXi	STRING
<input type="checkbox"/> VMWARE-SYSTEM-MIB::vmwProdVersion.0	6.0.0	STRING
<input type="checkbox"/> VMWARE-SYSTEM-MIB::vmwProdBuild.0	2494585	STRING
<input type="checkbox"/> VMWARE-SYSTEM-MIB::vmwProdUpdate.0	0	STRING
<input type="checkbox"/> VMWARE-SYSTEM-MIB::vmwProdPatch.0	0	STRING



The 'Create Probe' dialog box is shown. It contains the following fields and options:

- OID:** .1.3.6.1.4.1.6876.1.1.0
- Probe Name:** (empty text field)
- Add to existing probe group**
 - Application shh probe** (dropdown menu)
- Create a new probe group**
 - Probe Group Name:** (empty text field)

Buttons for 'Cancel' and 'Create' are located at the bottom right.


9. When you select "Create Probe" a new box will open that will allow you to give the Probe a name and either save it to an existing Probe Group or create a new one.
10. Now you have a new Probe that will run the particular SNMP command you requested.

5. Arbitrator Maintenance


5.1. Backup and Restore the Arbitrator

This procedure backs up Insights Arbitrator, retrieves the backup files, and restores the system.

1. Configure the Arbitrator backup. See *Archive Tab*.
2. Restore the Arbitrator application from a backup:
 1. Log in to CLI as an admin.
 2. In the **Administration** menu, select **Backup Restore**, then click **OK**.




3. Select **Restore a backup**.



4. Optionally, run the `Fetch` command to retrieve backup files.
5. Select the local backup you wish to restore. Choose an option:
 - If you wish to restore data from the nightly backups, select `self`.
 - If you wish to restore from another source, including a remote backup of this device, then select the relevant source.

Note: Additional restore locations can (optionally) be retrieved using the `Fetch` command, or the **Restore** screen selects this device as the target of the `rsyncToArb` method.

For example, the image displays two potential restore locations: `172.30.42.169` and `dh`



6. Select the data types to restore.

```
self
Please choose a data type to restore:
 1. All
 2. Avaya
 3. CISCO
 4. Config
 5. DEM
 6. Identity
 7. NDX
 8. Pexip
 9. Polycom
10. Themes
11. UHE
12. VDF
13. Webex
14. Zoom
15. DBDATA_ONLY

 0. (cancel)
```

7. Select the number of months to restore (0 to 60 or all).

```
self All
self All
How many months of data to restore? (0..60, all)
 (no number means cancel)
```

8. Confirm the restore.

```
self All 0
Requested data and configurations will be restored.
Existing data and configurations may be replaced/overwritten.
Are you sure you wish to restore the data (y/n)?
```


9. Monitor restore progress. A system message confirms when the restore is complete.

Important: Restoring Insights Arbitrator may take several hours, especially on larger systems and/or when restoring more data.

5.2. System Recovery


This procedure provides access to options that allow you to troubleshoot and recover Arbitrator services in the event of system errors.

1. Log in to CLI as an admin.
2. On the **Administration** menu, select **System Recovery**.



3. On the **System Recovery** menu, choose an option for the issue you're trying to resolve. Options are:

Fix corrupt NDX	May be used to repair the NDX. The NDX is the backbone of the “Search” screen in the user interface. If the “Search” screen displays zero results, the NDX may be corrupt. This option terminates the current NDX files and start a new NDX set of files.
Restart Arbitrator services	Allows you to restart the Arbitrator’s core services involved in collection, correlation, and alerting. This option is useful when attempting to debug a scenario where alerts are not firing.
Restart OpenLDAP	Used specifically for restarting the OpenLDAP service. This option is useful when attempting to debug authentication issues in the user interface.
Reset DB sequence counters	This option provides an optional (last resort) method for resolving a rare scenario when alerts stop firing. If you’ve exhausted the normal troubleshooting checks for alerting, this option may be used as a final resort. This method has been shown to fix rare issues in the past, and is provided as an option until the issue may be auto-detected and automatically repaired.



5.3. Network Observability

5.3.1. Overview

Network observability is configured on the Arbitrator as a set of probe scripts that collect and analyze data from the customer's network devices.

Note: The probe scripts comprise a set of SNMP v2 scripts and a set of SNMP v3 scripts. Both v2 and v3 of the SNMP scripts perform the same function. The version you'll use depends on whether your device supports SNMP v2 or SNMP v3.

Data is presented for analysis via read-only network observability reference dashboards in the Insights Dashboard system. The dashboards have read access to the database tables on Arbitrator, and allow you to determine in greater detail why alerts have occurred.

Related Topics

- [Probe Configuration](#)
- [Asset Configuration](#)
- VOSS Reference Dashboards in the Dashboard Administration Guide

5.3.2. Configure Network Observability Probe Groups

This procedure configures network observability probe groups in Arbitrator.

1. Log in to the Arbitrator.
2. Click the toolbar Wrench icon to open the **System Configuration** interface.
3. Click the **Probes** icon to open the **Probe Configuration** page.
4. Click the Plus icon (+) at the bottom of the **Groups** panel to add the first probe group, then fill out a probe group name, and tab out of the field to add the probe group.

Important: We have provided a recommended configuration of the following four probe groups, including a recommended naming convention and probe configuration parameters, in [Network Observability](#):

- Network Observability 5 min
- Network Observability 10 min
- Network Observability SNMP 10 min
- Network Observability SNMP 5 min,

For example, for the first probe group you add, you can use *Network Observability 5 min* as the probe group name.


5. Add the probes for the probe group you added.

Note: It is recommended that you use the probe configuration parameters provided in the table, in [Network Observability](#).

- On the **Probes** panel, at **Select Category**, click the down-arrow, then select **Network Observability**.

Note: Clear the **Custom** checkbox to display the **Select Category** drop-down.

- Fill out the probe name.
- Select the relevant script, based on the recommended configuration in [Network Observability](#).
- If relevant for the probe you're configuring, you will need to provide SNMP credentials.
- Click the check icon to save the probe.



6. Repeat these steps to add the rest of the probe groups and probes required for network observability, based on the settings provided in *Network Observability*.
7. Click **Save**.

Next steps:

- Once you've set up the probe groups, the SNMP probe groups are applied to the device you're collecting data from.
- Assign customers to assets. For details, see *Asset Configuration*

In order for the network observability probe groups to return useful data, the corresponding assets should have “customer” and “site” assignment. This is done via the **Asset Configuration** menu in Arbitrator.

- In **Asset Configuration**, locate the Arbitrator (in the **Assets** panel).
 - Click on the wrench icon to configure the monitor profile.
 - Drag the relevant probe group into the **Templates/Profiles** panel, then click the wrench icon to set the frequency, as per the settings for the probe group in *Network Observability*.
- Repeat this step to add other probe groups, and to configure their frequency.
- Click **Update**.

5.3.3. Recommended Network Observability Probe Group Configuration

This topic describes a recommended setup for the four probe groups required for optimal network observability.

The table describes the recommended network observability probe group configuration:

Probe Group	Configuration
1. Network Observability 5 min	<p>There are two probes to set up for this probe group:</p> <ol style="list-style-type: none"> 1. Network Observability Asset Impact This probe detects the impact of network observability alarms on locations. <ul style="list-style-type: none"> • Scripts to use with this probe: <ul style="list-style-type: none"> – <code>netob-asset-impact-assessment.sh</code> • Category: Network Observability • Parameters: N/A • Applied to: Arbitrator • Frequency: 5 minutes • Credentials: N/A 2. Network Observability Interface Event Detections This probe detects the interface counter changes for discards and errors. <ul style="list-style-type: none"> • Script to use with this probe: <ul style="list-style-type: none"> – <code>netob-alarm-probe-interface-stats.sh</code> • Category: Network Observability • Parameters: Use defaults, unless customization is required. • Applied to: Arbitrator • Frequency: 5 minutes • Credentials: N/A
2. Network Observability 10 min	<p>This probe group contains one probe. The probe detects the cbqoscm counter changes.</p> <ul style="list-style-type: none"> • Probe name: Network Observability CB QoS Event Detections • Script to use with this probe: <ul style="list-style-type: none"> – <code>netob-alarm-probe-cbqoscm-stats.sh</code> • Category: Network Observability • Parameters: Use defaults, unless customization is required. • Applied to: Arbitrator • Frequency: 10 minutes • Credentials: N/A
3. Network Observability SNMP 10 min	<p>This probe group contains one probe. The probe is used for netob-cisco-cbq-mib-stats-snmpv3 collection for group01.</p> <ul style="list-style-type: none"> • Probe name: Network Observability CBQ • Script to use with this probe - either of the following: <ul style="list-style-type: none"> – <code>netob-cisco-cbq-mib-stats-snmpv3.sh</code> – <code>netob-cisco-cbq-mib-stats-snmpv2c.sh</code> • Category: Network Observability • Parameters: Supply appropriate credentials, where applicable. • Applied to: Asset • Frequency: 10 minutes • Credentials: SNMP

Probe Group	Configuration
4. Network Observability SNMP 5 min	<p>This probe group contains one probe. The probe is used for netob-ifmib-interface-stats-snmpv3 collection for group01.</p> <ul style="list-style-type: none">• Probe name: Network Observability Interface• Script to use with this probe - either of the following:<ul style="list-style-type: none">– netob-ifmib-interface-stats-snmpv3.sh– netob-ifmib-interface-stats-snmpv2c.sh• Category: Network Observability• Parameters: Supply appropriate credentials, where applicable.• Applied to: Asset• Frequency: 5 minutes• Credentials: SNMP