

VOSS-4-UC Advanced Configuration Guide

Release 21.1

Sep 21, 2021

Legal Information

Please take careful note of the following legal notices:

- Copyright © 2021 VisionOSS Limited.
 All rights reserved.
- · VOSS, VisionOSS and VOSS-4-UC are trademarks of VisionOSS Limited.
- No part of this document may be reproduced or transmitted in any form without the prior written permission of VOSS.
- VOSS does not guarantee that this document is technically correct, complete, or that the product is free from
 minor flaws. VOSS endeavors to ensure that the information contained in this document is correct, whilst every
 effort is made to ensure the accuracy of such information, VOSS accepts no liability for any loss (however caused)
 sustained as a result of any error or omission in the same.
- This document is used entirely at the users own risk. VOSS cannot be held responsible or liable for any damage to property, loss of income, and or business disruption arising from the use of this document.
- The product capabilities described in this document and the actual capabilities of the product provided by VOSS
 are subject to change without notice.
- VOSS reserves the right to publish corrections to this document whenever VOSS deems it necessary.
- All vendor/product names mentioned in this document are registered trademarks and belong to their respective
 owners. VOSS does not own, nor is related to, these products and vendors. These terms have been included to
 showcase the potential of the VOSS solution and to simplify the deployment of these products with VOSS should
 you select to utilize them.

Security Information

This product may contain cryptographic features that may be subject to state and local country laws that govern the import, export, transfer and use of such features. The provision of this software does not imply that third-party authorization to import, export, distribute or use encryption in your particular region has been obtained. By using this product, you agree to comply with all applicable laws and regulations within your region of operation. If you require further assistance, please contact your dedicated VOSS support person.

Contents

1	What's New	1
	1.1 Advanced Configuration Guide: Release 20.1.1	
2	2.12 Global Settings	13 13 19 20 21
		_
3		23 25 25 26 26 27
3	System Monitoring 3.1 System Monitoring Configuration 3.2 System Monitoring Database Statistics 3.3 System Monitoring Model Counts 3.4 VOSS-4-UC Cluster Status 3.5 UC Apps Reachability 3.6 Worker Queue 3.7 Login Sessions	23 25 25 26 27 28 29 30 45 64 65
	System Monitoring 3.1 System Monitoring Configuration 3.2 System Monitoring Database Statistics 3.3 System Monitoring Model Counts 3.4 VOSS-4-UC Cluster Status 3.5 UC Apps Reachability 3.6 Worker Queue 3.7 Login Sessions Customization Overview 4.1 Feature Package Customization 4.2 GUI Customization 4.3 Theme Customization 4.4 Menu Customization 4.5 On-line Help 4.6 Scripts Move Customizations (Provider)	23 25 25 26 27 28 29 29 30 45 64 65

	6.1	Change LDAP User Sync from Top-Down to Bottom-Up	74
7	7.1 7.2 7.3 7.4 7.5 7.6	Com Configuration Configuration Overview Site Defaults Reference Named Macros Overview Quick Add Group Customization Quick Add Subscriber Configuration Smart Add Phone Configuration	80 81 82 82
8	Conf 8.1 8.2 8.3 8.4	Figuration Reference Reference Material Site Defaults Macros Quick Add Groups Configuration Template Reference Named Macro Reference	90 96
9	9.1 9.2 9.3 9.4	Macro Syntax	112 123
Ind	dex		193

1. What's New

1.1. Advanced Configuration Guide: Release 20.1.1

- EKB-4053: UserOPS Workflows in QuickAddSubscriber and relationSubscriberPhone results in CUCM Purge of existing Phones. See: Global Settings
- EKB-4160: Macro function to remove non ASCII characters. See: String Functions
- EKB-4642: Improve RIS API data collection performance. See: Activate Phone Status Service
- EKB-4642: Improve RIS API data collection performance. See: System Monitoring Configuration
- EKB-5144: Update default Phone Status collection to be enabled. See: Activate Phone Status Service
- EKB-5144: Update default Phone Status collection to be enabled. See: *System Monitoring Configuration*
- EKB-5682: Timestamp on internal directory number extra6 to be Melbourne time. See: Time Functions
- EKB-5780: UC app connectivity monitoring probes must be performed on each UN. See: *UC Apps Reachability*
- EKB-6669: Update data/Settings to skip workflows for ignored changes on device/ldap/userProxy. See: Data Sync Blacklist
- EKB-7768: Webex Room Device Activation for Workspace message is generated in error. See: *Time Functions*
- EKB-7914: Move Subscriber Line Template should be processed / evaluated at target site level. See: Named Macros - Site Defaults Line
- VOSS-551: User Management Overhaul (EKB-6537: Support for a mechanism to override authentication method for QAS and Data Sync) . See: *Global Settings*
- VOSS-651: Number Inventory Improvements. See: Number Management Functions
- VOSS-670: Small Enhancements 20.1.1 (EKB-3785: List view summary attributes must honor FDP title overrides). See: Field Display Policies
- VOSS-670: Small Enhancements 20.1.1 (EKB-3539: Add new field to Configuration Templates to define Feature Usage to enhance GUI rule filtering). See: Create a Configuration Template
- VOSS-670: Small Enhancements 20.1.1 (EKB-4868: Create menu diff tool) . See: Menu Diff Tool

1.2. Advanced Configuration Guide: Release 21.1

- EKB-10048: Allow fields to be exempt from device overwrite check in Settings. See: Device Overwrite
 Check Exemptions
- EKB-7436: Implement short term safe-guard against deleting a bulk of users. See: Pull Sync Delete Threshold
- EKB-7520: Add new function to return the Device Pool referenced by the least amount of Phones for a Site. See: CUCM and Device Functions
- EKB-7570: Create macro function to perform HTTP GET. See: HTTP Functions
- EKB-8033: New macro function regex_match required for EKB-7392. See: String Functions
- EKB-8205: Create new function, fn.generic_device_model_custom_operation, to return results of device model custom operation to workflow context. See: CUCM and Device Functions
- EKB-8222: Add new Direction in Macro Evaluator, fulltree, for searching up and down the hierarchy. See: SELECT FROM WHERE Macro Syntax
- EKB-9104: Flow through provisioning (Zero touch provisioning). See: Global Settings
- EKB-9170: Create new function fn.match_model_filter_criteria. See: Model Filters
- VOSS-725: Webex Teams Device / Hybrid Call Management. See: Global Settings
- VOSS-790: Pexip Support. See: Global Settings
- VOSS-794: Improve transaction log management (EKB-8517: Mechanism to override transaction log level for data sync execution). See: Transaction Log Levels
- VOSS-794: Improve transaction log management (EKB-8602: Preserve debug logs for failed transactions). See: Transaction Log Levels
- VOSS-794: Improve transaction log management (EKB-9184: Update tooltip for data/DataSync.transaction_log_level to call out default value when value is not set) . See: Transaction Log Levels
- VOSS-794: Improve transaction log management (EKB-9092: Create a view to allow users below sys hierarchy to change transaction log level). See: Manage System Settings
- VOSS-795: Multi-vendor Subscriber List and Dashboard (EKB-8082: Create Supported Vendor/Service Global Settings). See: Global Settings
- VOSS-832: Purge Number Inventory Tool. See: INI Purge Tool
- VOSS-835: Extended Webex Teams User and Workplace Management. See: Global Settings

2. Settings and Tools

Important: User who have access to and modify data/Settings entries should back these up (for example, export the Global instance JSON) prior to upgrading and subsequently restore the backup (for example, import the exported Global instance).

2.1. Login Banner

A banner, typically a security notice or user agreement, can be configured at a hierarchy level to show on the Administrator and Self-Service login page before login.

High level administrators who have access to the data/LoginBanner model can configure the banner. A banner can be created so that:

Only one instance is allowed per hierarchy

If an administrator or Self-Service user logs in and belongs to a hierarchy for which there is no defined login banner, the first banner higher up on the hierarchy is displayed. If no banners are configured, then the user logs in without a banner.

The banner text is displayed in the format that it is entered into the input box upon configuration.

When the banner is configured, users will see the banner displayed on the login page after they enter their credentials and when they click the **Login** button. An **Agree** and **Cancel** button is shown beneath the banner. Users then need to click the **Agree** button to complete the login. If they click **Cancel**, they are returned to the login page.

Note: This banner is independent of the text on the login screen that may contain a privacy policy reference. The privacy policy text and reference on the login page is configured as a part of the Login Page Details when managing a theme - see *Set the Login Page Theme and Text on the Legacy Admin Portal*.

2.2. Transaction Log Levels

For users that have access to the data/Settings model or view/DataSettings, the global levels of logging can be managed.

This level will affect the Log block of messages at the bottom of a selected transaction on the Transaction interface and does not for example affect the transaction or sub transaction Action and Detail information.

Log levels are *cumulative*, in other words, more detailed levels include all details from less detailed levels. The levels includes messages and have severity values as follows:

Level	Description	Severity
Disabled	disables all transaction log messages	999
Error	only displays error messages	40
Warning	also adds warning messages to above	30
Info	also adds informational messages to above	20
Verbose	also adds messages used for diagnostic purposes to above	15
Debug	also adds advanced diagnostic messages - for future use	10

- The Severity values are referenced (from value to value) in transaction details when the log level is changed on this setting or changed by lower level administrators from the **System Settings** menu. See: *Manage System Settings*.
- If a transaction fails, the Log block will include all entries with severity values larger than that of the default or selected level of logging.
- The log levels of data syncs can be set to override these global levels.

The transaction log level used for data sync and its immediate sub-transactions is by default set to Warning when it is not set.

For details, refer to the Create a Custom Data Sync topic in the Core Feature Guide.

2.3. Manage System Settings

Administrators at provider level as well as hcsadmin administrators have access to a **System Settings** menu under **Administration Tools**.

Transaction Log Level

Provider level and hcsadmin administrators can modify the Transaction Log Level - the level of verbosity of transaction logs.

The setting is available as a global setting to high level administrators who have access to the data/ Settings model. When an administrator first opens **System Settings**, the displayed value for the **Transaction Log Level** is the default in the global setting.

For a description of the available log levels, see: *Transaction Log Levels*

The settings are:

Disabled

- Error
- Warning
- Info
- Verbose
- Debug

The purpose of the setting is so that the log level can be changed according to need, for example to Verbose so that more details are available for immediate troubleshooting and customization work.

Note: A **Notes** section and warning is shown if the level is set to <code>Verbose</code> or <code>Debug</code>, reminding administrators that the retention period of such logs is shorter due to their increased size, which consequently reduces the date range of available logs for troubleshooting.

A typical use of this setting would be for troubleshooting: when a problem is encountered on a system and detailed logs need to be obtained. The steps could then be:

- 1. Toggle the log level to Verbose.
- 2. Reproduce the issue causing the problem.
- 3. Export the logs and forward them to VOSS support.
- 4. Toggle the log level back to Info.

2.4. File Extensions

For users with system administrator privileges to the data/Settings model, the valid file extensions can be managed.

By default, the following file extensions are in the Global instance of this model and are valid. This means that files with this extension can be uploaded to VOSS-4-UC:

- .cer
- .crt
- .der
- .gzip
- .json
- .key
- .pem
- .xlsx
- .xml
- · .zip
- · .png
- .jpg
- .jpeg

File extensions can be added or removed by this administrator. Files that do not have an extension that corresponds with an instance in this model, cannot be loaded or imported. An error message will display on the user interface to indicate that the file does not have a valid file extension.

2.5. Disable Device Logging

For users that have access to the data/Settings model, device logging can be managed.

If the Disable Device Logging check box is enabled, Unified CM AXL (and other external calls) requests and responses are not written to the transaction log. Generic driver requests, responses, template evaluations and macro evaluations are also not written to the transaction log.


These details will then *not* be shown for the relevant transactions under **Administration Tools > Transaction Log**.

2.6. Activate Phone Status Service

System administrators with access to data/Settings can see the **Activate Phone Status Service** check box that is enabled by default. This indicates that the real-time information (RIS) data collector service is enabled and is polling the Unified CM to obtain the latest phone registration status information for phone instances stored in the VOSS-4-UC database. The polling default interval is: 43200 seconds (12 hours).

For details, refer to the Metrics Collection topic in the Advanced Configuration Guide.

However, When viewing a list of phones, the **status** action can be carried out by an administrator who has been assigned a role that has an access profile to enable this action. By default, an administrator *above* provider level can carry out this task from the **Role Management > Access Profiles** menu - in this case, for relation/SubscriberPhone.




Carrying out this operation fetches the Unified CM phone IP address and status *directly* from the Unified CM and displays the data on the **Phones** list view **Registration Status** and **IP Address** columns, updating any existing data shown.

Important: Since the result of the **status** action is in real time, the current status of the list requires that the action carried out in order to see the latest values.

There is no caching of data resulting from this action. If any values show in the columns before carrying out this action, these would not be current, but are the cached values from the RIS data collector if it is enabled.

When carrying out the **status** action, the data in the **Registration Status** and **IP Address** columns can only be viewed.:

- The latest data only shows for the *current* list of phones on the GUI.
- The data in these columns is not stored in the database and cannot be exported.



Note:

- Whether the real-time information (RIS) data collector service is enabled or disabled, if the **status** action is carried out from the phones list view, the operation will *always* fetch and display the current information for the displayed phones directly from the device.
- The administrator's access profile associated with the role needs to allow the administrator to carry out the **status** action.
- The carrier-integrated Mobile device type is automatically added to the RIS API Excluded Device Types and therefore not fetched by the service.

When clearing or enabling the check box on data/Settings, log in on the platform command line interface (CLI) and restart the service:

\$ cluster run application app start voss-risapi_collector

7

2.6.1. Phone Status Service in the Logs

When clearing this setting and then restarting the (RIS) data collector service, an app.log entry will show: "message": "RIS API service disabled".

Refer to the Platform Guide for commands to inspect log files.

Example log entry below (line breaks added):

```
2020-03-26T20:06:00.346577+00:00 VOSS-UN-2 deviceapi.background.risapi INFO
{"process_id":24,
    "hostname":"VOSS-UN-2-voss-risapi-collector",
    "name":"deviceapi.background.risapi",
    "level":"INFO",
    "utc_iso_timestamp":"2020-03-26T22:06:00.346268",
    "request_uuid":null,
    "user_hierarchy":null,
    "user":null,
    "message":"RIS API service disabled",
    "line":330,
    "parent_process_id":1
}
```

2.7. Additional Role Access Profile Validation

For users with system administrator privileges to the data/Settings model, a setting called Additional Role Access Profile Validation is available as a check box to manage the available roles when an administrator creates Access Profiles.

When the Additional Role Access Profile Validation check box is enabled:

An administrator can only assign a role to a user if it is linked to an access profile with permissions that are in the subset of the administrator's own access profile. Role drop-down lists will therefore be restricted.

If the macro function fn.filter_roles_by_user_access_profile is used, the setting needs to be enabled for roles to be filtered.

• When the Additional Role Access Profile Validation check box is disabled:

An administrator can assign any role to a user, regardless of the administrator's own access profile. Role drop-down lists will therefore not be restricted.

If the macro function fn.filter_roles_by_user_access_profile is used, the roles will not be filtered.

By default, the Additional Role Access Profile Validation is disabled.

Refer to the macro topic Filter Role Functions for details on the use of the fn. filter_roles_by_user_access_profile function.

2.8. File Upload Limitations

By default, the following file limitations apply:

- Maximum Upload File Size: 209715200 bytes (200MB)
- Time-To-Live for Uploaded Files: 24 (clean up every 24 hours)

For users with permissions to the Global instance of the data/Settings datamodel, the upload file size and its time-to-live on the database can be configured.

Files are uploaded to the system database during such activities as:

- Bulk Load
- · JSON import
- · Theme upload
- · any other file upload activity

The time-to-live value applies to uploaded files that have not been used, in other words, imported or processed. By default, a check is done every 24 hours for such files, after which time they are removed.

2.9. Time-To-Live for Uploaded Files

For users with system administrator privileges to the data/Settings model, the time-to-live for uploaded files can be managed.

Note: Files that are uploaded from file management menus on the user interface and listed as instances of data/File are not affected.

Uploaded Bulk Load files and imported JSON files are affected, however:

- For Bulk Load files, the file is kept for as long as there is an instance of data/BulkLoad attached to it. So a schedule that is more than 24 hours in the future is not impacted, because when we schedule a bulk load for the future, we create a data/BulkLoad instance. The instance is cleared when the Bulk Load is executed.
- Monthly License Reports that are uploaded to the database by the internal schedule are not removed. For more details, refer to the License Feature Guide.

2.10. Data Sync Blacklist

Administrators with permissions to access the Global instance of the settings in the data/Settings model, can create a list of device attributes that will *not* trigger any update workflows that may have been defined to execute during the data sync. These attributes are here called Data Sync Blacklist attributes and are excluded from data sync considerations.

The reason for this list of attributes is that while data sync operations can have a performance impact, some data sync attribute changes do not require data sync workflows to be carried out.

9

Note however that *the local device cache will still be updated with the updated attribute data*. No update workflows will be run, though. The transaction logs will indicate the updated device cache, but the transactions for these attributes instances will show as:

"Device changes on blacklisted attributes only. Updating cache, skipping workflows."

Note: After release 20.1.1 or applying patch EKB-4362-19.2.1_patch, the previously blacklisted LDAP attributes are no *longer imported* during LDAP syncronization:

For device/ldap/user:

- logonCount
- adminCount
- lastLogonTimestamp
- whenCreated
- uSNCreated
- badPasswordTime
- pwdLastSet
- lastLogon
- · whenChanged
- badPwdCount
- accountExpires
- uSNChanged
- lastLogofflastLogoff

A number of blacklisted attributes have been added by default:

2.10.1. Blacklisted device/ldap/user

- For device/ldap/user:
 - logonCount
 - adminCount
 - lastLogonTimestamp
 - whenCreated
 - uSNCreated
 - badPasswordTime
 - pwdLastSet
 - lastLogon
 - whenChanged
 - badPwdCount

- accountExpires
- uSNChanged
- lastLogoff
- userPassword

2.10.2. Blacklisted device/cucm/User

- For device/cucm/User:
 - status
 - primaryDevice
 - attendeesAccessCode
 - displayName
 - enableUserToHostConferenceNow
 - pinCredentials
 - passwordCredentials
 - associatedRemoteDestinationProfiles

2.10.3. Blacklisted device/cucm/Phone

- For device/cucm/Phone:
 - keyOrder
 - elinGroup
 - ecKeySize

2.10.4. Blacklisted device/ldap/userProxy

- For device/ldap/userProxy:
 - accountExpires
 - adminCount
 - badPasswordTime
 - badPwdCount
 - bind_dn
 - dSCorePropagationData
 - distinguishedName
 - employeeID
 - homeMDB
 - instanceType

- lastLogon
- lastLogoff
- lastLogonTimestamp
- legacyExchangeDN
- logonCount
- mDBUseDefaults
- mailNickname
- manager
- msExchArchiveQuota
- msExchArchiveWarnQuota
- msExchBlockedSendersHash
- msExchCalendarLoggingQuota
- msExchDumpsterQuota
- msExchDumpsterWarningQuota
- msExchELCMailboxFlags
- msExchHomeServerName
- msExchMailboxGuid
- msExchMailboxSecurityDescriptor
- msExchMobileAllowedDeviceIDs
- msExchMobileBlockedDeviceIDs
- msExchMobileMailboxFlags
- msExchPoliciesIncluded
- msExchRBACPolicyLink
- msExchRecipientDisplayType
- msExchRecipientTypeDetails
- msExchSafeSendersHash
- msExchTextMessagingState
- msExchUMDtmfMap
- msExchUserAccountControl
- msExchVersion
- msExchWhenMailboxCreated
- objectCategory
- objectClass
- objectGUID
- objectSid
- physicalDeliveryOfficeName

- primaryGroupID
- protocolSettings
- proxyAddresses
- pwdLastSet
- sAMAccountType
- showInAddressBook
- textEncodedORAddress
- uSNChanged
- uSNCreated
- userAccountControl
- whenChanged
- whenCreated
- userPassword

2.11. Device Overwrite Check Exemptions

Administrators with permissions to access the Global instance of the settings in the data/Settings model, can create a list of fields to be excluded from device overwrite checking.

This means that if the field changes on the device, it will *not* be overwritten by data in VOSS-4-UC. The most common situation where this might be necessary is where a device field changes, but does not affect the data on VOSS-4-UC, because the data is treated as read only in VOSS-4-UC.

2.12. Global Settings

Provider administrators and higher have access to a **Global Settings** customization menu that allows for the configuration of a number of settings across all hierarchies or per individual hierarchy. This topic describes the tabs on the Global Settings page (default menu: **Customizations > Global Settings**)

In the Admin Portal, the read-only value below the drop-down is the current setting (True/False), for options:

- Inherit the service is enabled/disabled based on the setting at the hierarchy above the current one.
- Yes the service is enabled at the current hierarchy.
- No the service is disabled at the current hierarchy.

To change inherited settings, see *How to Change Inherited Settings*.

2.12.1. Number Inventory Tab

Enforce HCS Dialplan Rules:

When enabled, dial plan workflows enforce HCS Rules when provisioning Customers, Countries, Site and so on. Default = **Inherit**. If your deployment uses a custom or specific dial plan which does not conform to the HCS rules, this setting should be set to **No**.

• Include the Number Inventory description in all number drop-downs:

This setting defines whether descriptions for the numbers (which can be added when the number inventory is managed via the **Number Management** menu), display along with the numbers in the drop-down lists. For example, let's say you have a number and its description as follows: 1000 - CEO Internal. When this setting is enabled (Yes), both the number (1000) and its description displays in the lists (when using features such as Quick Add Subscriber). The default is No.

Enable Number Inventory Cooling:

This setting defines the availability of numbers in the system when a phone, subscriber, or service associated with the number is deleted, and the number is no longer associated with these entities.

The table describes the options for this setting:

Op- tion	Description
In- herit	When set to True, number inventory cooling is enabled or disabled based on the setting defined for number inventory cooling at a higher level in the hierarchy.
True	Enabled, at the hierarchy level you're at. Numbers associated with deleted entities are kept in a cooled state for a specified number of days (based on the value defined in the Number Inventory Cooling Duration (Days) field. Numbers in a cooled state are unavailable in the system until the cooling period end date is reached, unless they are manually released before the end cooling period end date.
False	Default. Number inventory cooling is disabled by default.

Number Inventory Cooling Duration (Days):

When number inventory cooling is enabled (True), this field defines the period (number of days) the number is kept in a cooled state and unavailable for association with a phone user, or service. The default is 30 days.

Related Topics

- · Number Cooling in the Core Feature Guide
- Number Cooling Auto Expiry Schedule in the Advanced Configuration Guide

2.12.2. Webex Teams Tab

 Retain a Webex Teams User when a Subscriber is deleted / Send notification when the Webex Teams Refresh Token expires

Default is No (no message will be sent). Values can be inherited or set as required.

Webex Teams Refresh Token expires threshold (in seconds)

The default (inherited) value is 172800. You can change the value if required.


· Automatically apply default calling behaviour on Webex Teams user data sync

Defines whether to apply default calling behavior (configured in customer settings), when syncing users from the Webex Control Hub. The default is **No**. The setting is also selected for the service.

· Generate and send Webex Teams User CSV file via Webex Teams message

Defines whether a CSV file is generated and sent as a Webex Teams message. The default is **No**. The CSV file can be imported into Webex Teams Control Hub to update the users.

Example of email message with attached CSV file:




Email group containing recipients of the generated Webex Teams user CSV file

The selected email group: the recipients of the Webex Teams message containing the generated CSV file. The email group can be set up.

Send manual Webex Teams Workspace configuration steps via Webex Teams message

Defines whether manual configuration steps (on Webex Teams Control Hub) are to be sent on creation or modification of a Webex Teams workspace. Default is **No**.

If enabled, the steps will be sent via a Webex Teams message, for example:



· Email group containing recipients of the manual Control Hub steps

The selected email group: the recipients of the Webex Teams message containing the manual configuration steps (on Webex Teams Control Hub). The email group can be set up.

Quick Add Group for Hybrid Calling Workspace Unified CM users

Defines the Quick Add Group to use when creating dummy Unified CM users with line and device for Webex Teams workspace hybrid calling.

Related Topics

- · Quick Add Subscriber Group in the Core Feature Guide
- · Email in the Core Feature Guide
- · Email Groups in the Core Feature Guide
- Create Webex Teams Service in the Core Feature Guide

2.12.3. **Pexip Conference**

Retain a Pexip Conference when a Subscriber is deleted

Defines whether the Pexip conference set up from the subscriber interface is to be removed when the subscriber is deleted. By default the setting is inherited from the hierarchy level directly above the current one.

2.12.4. **Email Tab**

Allow welcome email to be sent to user after Quick Add Subscriber

Defines whether an email is sent to a user when added via Quick Add Subscriber. The default is **No.**

When set to Yes, and a SMTP server is set up (via the Apps Management menu), then selecting the option to send an email when using Quick Add Subscriber, a welcome email is sent to the new subscriber.

Related Topics

SMPT Server in the Core Feature Guide

2.12.5. **Phones Tab**

This tab configures the global settings of phones for a site.

Note: These settings only apply to phones within the same site; both the re-added phone and the existing phone must be on the same site.

Delete existing Unassigned Phone when re-adding an identical Phone

This setting defines whether you can delete an existing, unassigned phone (that is, a phone without an owner), when re-adding a phone with the same name and type.

The current value for the setting displays below the drop-down. The default is *Inherit* (False). This means that if a phone with the same name and product type is re-added to the system in a Quick-AddSubscriber bulk load or when updating a subscriber, then by default it is not overwritten.

The table describes the global setting options for phones:

Set- ting	Description
Inherit	Default (False). When set to <i>Inherit</i> , the setting is inherited from the hierarchy above the current one.
Yes (True)	Allows you to re-add a phone with the same name and phone type, provided the new phone and the existing phone are on the same site.
No (False)	Does not allow overwrite (replacement) of the existing phone with a phone that has the same name and phone type.

2.12.6. User Tab

When a user is either synced into or added manually on VOSS-4-UC, these settings apply by default. The settings can however be modified when adding a user from the **User Management** menu.

User Default Auth Method

The default authentication method to use a user is synced in or added manually. The default is **Local** (inherited).

Related Topics

• User Authentication Methods in the Core Feature Guide.

2.12.7. Flow Through Provisioning Tab

This tab defines options for sync with flow through provisioning.

- Enable Flow Through Provisioning: When enabled, VOSS-4-UC allows for auto-provisioning users and services during user sync from devices. The default is No.
- Enable Provisioning after Add Sync: Enables/disables provisioning on LDAP after an add sync completes. The default is No (disabled).
- **Subscriber Criteria**: Defines the default flow through provisioning criteria. See *Flow Through Provisioning Criteria* in the Core Feature Guide.

2.12.8. Enabled Services Tab

This tab defines the global settings for enabling/disabling services for different vendors, such as Cisco or Microsoft. Options are Inherit, or Yes/No (True/False).

When provisioning services from two or more vendors, the global setting is the first of a number of system verification checks. For example, when the **Enable Cisco CUCM** global setting is set to **Yes** (enabled), the administrator can provision a subscriber with new CUCM services (such as a Cisco phone, Jabber, and extension mobility), only if the CUCM device check (server installed), entitlement profile check, and field display policy check all pass the verification check. In the same way, if for example, the **Enable Microsoft** global setting is set to **No** (disabled), and all other checks are set to enabled, existing Microsoft services can be viewed but new Microsoft services cannot be provisioned.

Note: By default, for new installs, the global setting for the following services are inherited from higher levels in the hierarchy (Inherit set to True/enabled):

- Cisco CUCM
- · Cisco CUCX
- · Cisco WebEx
- Cisco Webex Teams
- Cisco CCX

When upgrading to a version of the system that allows multi-vendor subscribers, the default setting for services other than these 5 services is Inherit (False). To provision services to new subscribers (added after an upgrade), you will need to enable the vendor service in global settings.

Related Topics

- · Multi-vendor Subscribers in the Core Feature Guide
- Role-based Access for Multi-vendor Subscriber in the Core Feature Guide
- Configure Multi-vendor Subscribers in the Core Feature Guide

2.12.9. How to Change Inherited Settings

- For numeric inherited values, for example, for "Number Inventory Cooling Duration (Days)" or "Webex Teams Refresh Token expires threshold (in seconds)"), you can overwrite the word "Inherit" with the required value, for example, 45, and save your changes. If the inherited value is already overwritten, for example, the value is already 45, then overwrite this value with the new value.
- For inherited values that are Yes/No (True/False), select an alternative from the drop-down (either Yes, No, or Inherit). This may change the current value.

2.13. Number Cooling Auto Expiry Schedule

The Number Cooling Auto Expiry Schedule (IniCoolingExpiryCleanupService) is a background process that runs daily to poll the Cooling End Date field on the Number Inventory list view, in order to determine which numbers have completed their cooling period.

Numbers that have reached their cooling end date are returned to the pool of available numbers at the specific hierarchy.

This process picks up any numbers with a cooling end date within the last 20 days. In this way, it can identify any numbers that reached their cooling end date while the system was down, or if the schedule was disabled for any reason.

Numbers with a cooling end date older than 20 days must be removed from cooling manually. A system administrator can manually release any cooled number, regardless of its cooling end date.

Important: An hesadmin user (or higher) can view and manage the Number Cooling Auto Expiry Schedule (IniCoolingExpiryCleanupService) from the Scheduling list view.

While the hcsadmin user can edit this schedule, for example change the execution time or timezone, the schedule must run every day and should not be disabled.

See Also:

- · Number Cooling in the Core Feature Guide
- Global Settings

2.14. SMTP Server

A SMTP server can be configured via the **Apps Management** menu at the relevant hierarchy to allow VOSS-4-UC to send email messages.

Email functionality is available for the following:

Quick Add Subscriber (QAS)

When email is enabled in the Global Settings (Email tab), you can select a checkbox on QAS to send a welcome email to new subscribers added via QAS.

· File Transfer Destinations

Configured by high level system administrators to to transfer audit data for licensing. See the Licensing and Subscriber Data Export Guide.

Add a SMPT Server

This procedure adds a SMTP server at a hierarchy level.

Prerequisites:

• Enable emails in the Global Settings (Email tab).

Perform these steps:

1. Log in to the Admin Portal, at the hierarchy where you wish to add a SMPT server.

Note: You may only set up one SMTP server at each hierarchy level. Hierarchies below the hierarchy where the SMTP server is set up can use the SMTP server at the hierarchy above; that is, sites can use the SMTP server set up at the customer level.

- 2. Go to (default menus) Apps Management > SMTP.
- 3. Click the toolbar Plus sign (+) to add a new SMTP server.
- 4. On the SMTP Server form, configure details for the new SMTP server:
 - Add name for the SMTP server, and a description for the email account.
 - Enter the SMTP server hostname and port number.
 - Select **Secure** to use the SSL protocol for establishing a connection to the SMTP server.
 - Enter username and password credentials for establishing a connection to the SMTP server.

Related Topics

· Email in the Core Feature Guide

2.15. Associate and Disassociate Devices to Application Users

A utility to associate and disassociate devices to Unified CM application users can be made available by high level administrators so that it shows on administrator menus on the user interface.

The utility simplifies this association and disassociation of a large number of Phones, CTI Route Points or Device Profiles to app users (device/cucm/AppUser). This would for example be in the case of large contact center deployments.

The model to expose on the administrator menu layout is <code>view/AddRemoveDeviceAppUser</code>. This menu can be available from the Legacy Admin Portal or Admin Portal. No Access Profile updates are needed for the default administrator access profiles.

For details on customizing menu layouts, see *Create a Menu Layout* in the Core Feature Guide.

2.15.1. Procedure

Important: The utility is available only at site level, so that only devices and device profiles at that level are available for management.

1. Select an **Application User** to manage.

The list of application users are those at and above the current site hierarchy.

You can associate **Devices** and **Device Profiles** with the same application user by means of side-by-side transfer boxes.

- 2. Choose the **Action**: either to associate or disassociate devices or device profiles.
 - When associating, only devices or device profiles not associated to the user at the current hierarchy are shown in the **Available** transfer box.
 - When disassociating, only devices or device profiles associated to the user at the current hierarchy are shown in the Available transfer box.
- 3. Optionally, add a substring filter in the **Filter Devices** or **Filter Device Profiles**.
- 4. Manage the items in the **Available** and **Selected** transfer boxes.

Note:

- Since the transfer boxes can only list 200 items, filters should be chosen to manage more items. The filter uses the "contains" case insensitive method. A notification is however displayed showing the total number of items.
- The Legacy Admin Portal transfer boxes controls do not include a "transfer all" control the muli-select of items in the "from" box is required.
- In the Admin Portal, a filter is available within the transfer boxes. This filter only applies to the 200 items (or less) within the transfer box.
- 5. Click Save to carry out the selected action.

Inspect the transaction log to verify the action. The **Detail** message includes the username of the app user.

Note: A database lock is used in the resulting transaction in order to ensure parallel transactions do not conflict.

2.16. INI Purge Tool

Number Inventory entries can be deleted in bulk by using the INI Purge Tool. High level administrators with access to the view called <code>INI_Purge_Tool_View</code> can expose this tool for user by updating menu layouts and access profiles for administrators.

Important: This Tool has been designed to remove DNs *without* taking into account the Status of the DN, so that DNs can be completely removed and then redeployed. In normal circumstances you cannot delete a DN if it is in use by a Phone.

For example, DNs may have been deployed incorrectly at Site level instead of at Customer level. You can therefore "Purge" all the DNs entries at the Site and re-add them at Customer level. The DN Audit Tool then needs to be run to update the DNs to the correct Status.

Using the INI Purge Tool

- 1. Navigate to the required hierarchy and select the INI_Purge_Tool_View.
- 2. From the Ini Purge Tool View form, an INI Option can be selected.

Note: Special characters in INI entry numbers are also supported, for example 1 * 6010.

The drop down list options are:

- All INI at Hierarchy: applies to all INI numbers at the current hierarchy.
- Range of INI Entries: exposes Range Start Number and Range End Number drop down lists to choose the range.
- Picked List of INI Entries: exposes Picked INI Entries transfer boxes: Available and Selected.
 to choose a selection of entries.
- Specific INI Entry: provides a Specific INI Entry drop down list to select a single entry.
- 3. Click **Save** to carry out the purge task.

Inspect the log from the **Transaction** menu - the **Action** carried out is a Bulk Delete from the Internal Number Inventory. Deleted numbers are removed and are not available from the **Internal Number Inventory** list view.

Note: Where more than 1000 entries are to be purged, the transaction will show sub-transactions deleting the entries in chunks of 1000. A successful sub-transaction then shows the message per chunk: "[1000 / 1000] were deleted successfully".

3. System Monitoring

3.1. System Monitoring Configuration

A sysadmin administrator can access the **System Monitoring menu (menu model**: data/SystemMonitoringConfig) to manage:

- A number of alerts that will trigger SNMP traps
- · Metrics collection

Default values are set in an instance called Global.

3.1.1. Alerts

From the Alerts tab on the Configuration menu, the following settings and options can be managed:

- Database Size Threshold (GB): the default size is 200 GB
- Database Index Size Threshold (GB): the default size is 50 GB
- Database Queue Size Threshold: the default size is 500
- Transaction Failures to Alert: errors for operations on model types.

The default operation is all Import operations on all data models (data/*)

For the configured alerts, SNMP traps are generated upon failure of the transaction. Refer to the System Monitoring SNMP topic in the Platform Guide for details and examples of the traps.

3.1.2. Metrics Collection

The Metric Collection tab shows:

 A configurable RIS API data collector interval which is the time interval that the real-time information (RIS) data collector service polls the Unified CM to obtain the latest phone registration status information for phone instances stored in in the VOSS-4-UC database.

The value is in seconds and the default interval is: 43200 seconds (12 hours) Refer to the Best Practices Guide for further information if this interval needs to be modified.

Note that the **Cisco RIS Data Collector** service needs to be enabled and running on the Unified CM publisher.

The RIS data collector service updates the current registration status and/or IP address from the Unified CM Registration Status and IP address at the specified interval - for all clusters in the system. The **Phones** list view show **Registration Status** and **IP Address** columns containing this data.

The status of the collector service can be checked with the the platform CLI **app status** command - seen as <code>voss-risapi_collector</code> in the example console output snippet below:

Note:

 There is an Activate Phone Status Service check box in data/Settings that is selected by default. Real time data collection is available when this check box is selected. Phone status data is then fetched directly from the Unified CM and shown on the Phones list view. See: Activate Phone Status Service.

There is also a macro function <code>get_phone_status</code> available to return this Phone data, given as input parameters:

- a phone PKID
- followed by a comma and then exactly one RIS API field name.

The fields below are for example used in the VOSS-4-UC Admin Portal list view of Phones:

- * status
- * ip_address
- * cm_node

To see a full list of available fields, run the macro function without RIS API field names or refer to the Cisco RIS API documentation.

For example:

```
{{fn.get_phone_status}
5ca2b90bce894e0014d488fb,
status}}
```

output: "Registered"

3.2. System Monitoring Database Statistics

The sysadmin user has access to the **Database Statistics** menu (menu model: data/MetricDatabaseCollectionStats) that shows the weekly and monthly collection metrics internal database collections:

- The Group Number corresponds to the number of the Grouping month or week of the year respectively.
- The Top Collections by Data Size list shows individual data collections by name and sorted by size displayed in bytes.
- The **Top Collections by Index Size** list shows individual data collection indexes by collection name and sorted by index size displayed in bytes.
- The **Top Collections by Number of Documents** list shows data collection names by collection name and sorted by number of documents displayed as an integer.

The **Configuration** menu allows for SNMP alerts to be configured if thresholds are reached in total Data Size and Index Size.

3.3. System Monitoring Model Counts

The sysadmin user defines a list of Models to Aggregate on the Metric Collection tab of the Configuration menu (menu model: data/SystemMonitoringConfig). By default, the following models are included in the list:

device/cucm/CallPickupGroup device/uccx/Agent device/uccx/Team device/uccx/ContactServiceQueue device/uccx/ResourceGroup data/BaseSiteDAT device/cucm/User device/cucm/Phone device/cucm/HuntPilot data/InternalNumberInventory data/HcsDpE164InventoryDAT device/cucm/Line device/cucm/User device/cucm/DeviceProfile device/cuc/User device/spark/User

For these models, counts are collected daily. Daily, weekly and monthly aggregates at a particular hierarchy: *Provider, Customer or Site* are then stored. In other words, the counts include all hierarchy nodes below the particular hierarchy.

In the instance details, the **Group Number** is then the nth day or week of the year.

Note: For daily aggregates, only the most recent daily aggregate of the week is stored. Previous daily aggregates are aggregated into this daily aggregate and are then deleted.

A particular daily or weekly Model Counts instance will then show the **Average Count** of instances as specified in the **Models to Aggregate** list.

The data is also displayed as usage charts on the Business Admin Portal.

3.4. VOSS-4-UC Cluster Status

The sysadmin user has access to the VOSS-4-UC Cluster Status menu (menu model: data/MonitoringCluster) that shows aggregated VOSS-4-UC cluster Round Trip Delay Time (RTT) metrics at hourly and daily intervals.

Note:

- The retention period for data is 1 month.
- This metric uses the same data as the cluster check CLI command shows. See the Cluster Check topic in the Platform Guide.
- The Interval indicates the time interval for the entry: hourly or daily.
 - Hourly intervals aggregate samples collected 15 minute intervals. Daily intervals aggregate hourly intervals.
- The Start and End values are the time stamps for the interval. The difference corresponds with the selected Interval.
- The Source host and Destination port are the IP addresses of the nodes in the cluster.
 - Port 27020: database connectivity
 - Port 8443: HTTPS connectivity

For example, if **Source host** is 192.168.100.7 and **Destination port** is 192.168.100.6:27020, then database connectivity is monitored between 192.168.100.7 and 192.168.100.6:27020.

• The **Failures** is the number of connection failures between **Source host** and **Destination port** over the interval.

Failures would also generate alerts if an SNMP trap is configured.

• The Avg TCP RTT (ms) is the average RTT in milliseconds over the interval for a successful connection.

3.5. UC Apps Reachability

Provider administrators and higher have access to the **System Monitoring** menus:

- Unity Connection (data/MonitoringCuc)
- Call Manager (data/MonitoringCucm)
- HCMF (data/MonitoringHcmf)
- LDAP (data/MonitoringLdap)

The displayed data is the aggregated reachability and Round Trip Delay Time (RTT) for a UC app. Reachability is tested from *all* unified nodes.

- The Interval indicates the configured time interval for the entry: hourly or daily.
 - Hourly intervals aggregate samples collected 15 minute intervals. Daily intervals aggregate hourly intervals.
- The Start and End values are the time stamps for the interval. The difference corresponds with the selected Interval.
- The Unified Node is the node name of the source unified node.
- The Host name or IP is the IP addresses and port of the UC app.
 - Port 8443: HTTPS connectivity
- The Avg TCP RTT (ms) is the average RTT in milliseconds over the interval for a successful connection.

The details of a data instance also show the maximum RTT (Max Tcp RTT) during the interval.

If the average RTT exceeds 400 ms, an alert is also triggered.

• The Failures is the number of connection failures to the UC app Host name or IP over the interval.

For example, if the number of failures is 4 and the **Interval** is set to *hourly*, then all 4 reachability checks for the interval failed. Equally, if the **interval** is set to *daily* and all reachability checks failed, the value is 96 (24 x 4 hourly).

The details of a data instance with failures show the network error messages in the **Errors** group.

• The Located At column shows the hierarchy of the UC app.

Failures would also generate alerts if an SNMP trap is configured.

3.6. Worker Queue

Provider administrators and higher have access to the Worker Queue menu (data/MonitoringQueue). Data is retained for 1 month.

The displayed data is the aggregated number of transaction requests per processing node and configured interval.

- The Interval indicates the configured time interval for the entry: hourly or daily.
 - Hourly intervals aggregate samples collected 15 minute intervals. Daily intervals aggregate hourly intervals.
- The Start and End values are the time stamps for the interval. The difference corresponds with the selected Interval.
 - For the same **Start** and **End** timestamp, an entry is shown for each **Processing node** showing the combination of **Status**, **Priority** and **Tx level**.
- Status: Transaction process status: "Queued" or "Processing".
- Priority: Transaction priority: Low, Normal or High
- Tx level: Transaction level: either parent or child transaction.
- Processing node: the node that carried out the transaction.
- Avg Transactions: the average of the Max Transactions and Min Transactions for the selected Interval.

Note: The record detail also shows the **Min Transactions** and **Max Transactions** for the configured interval. These values reflect the sampling in the interval. For example, if the **Interval** is hourly and **Min Transactions** is 0, then one or more of the 15-minute sampling intervals recorded no transactions.

• The **Located At** column shows the hierarchy at which the transaction was run.

Note: If the value shows as sys (System), this includes all transactions at sys level and lower.

Also refer to the use of the voss worker and voss workers commands in the Platform Guide.

3.7. Login Sessions

Provider administrators and higher have access to the **Login Sessions** menu (data/MonitoringSessions).

- The Interval indicates the configured time interval for the entry: hourly or daily.
 - Hourly intervals aggregate samples collected at 15 minute intervals. Daily intervals aggregate hourly intervals.
- The Start and End values are the time stamps for the interval.
- Interface: The user interface to which the limit applies: administration or selfservice.
- Max sessions: maximum number of sessions, for example in any of the 15-minute sampling records during an hourly interval.
- **Utilization** %: utilization percentage for the interval in accordance with the defined *customer* session limits (max sessions / defined limit).

By default, the following limits apply:

- per customer administration: 10
- per customer selfservice: 1000
- The **Located At** column shows the hierarchy under which all sessions for a given entry are being counted. The sessions being counted are either by administrator or Self-service.

Note: The values reflected for at the sys hierarchy are global totals across all hierarchies, and the utilization percentage is calculated against the global limits.

Also refer to the use of the **voss session-limits** commands, for example to show and manage session limits, in the Platform Guide.

4. Customization Overview

4.1. Feature Package Customization

The system makes use of components called *models* that can be created and modified. The primary types of models are:

- Data Models that are used to capture and store data.
- Device Models that represent components of available network devices.

A mechanism is available for higher level administrators to customize:

- how different attributes of a form are displayed (using Field Display Policies):
 - visibility (hidden / visible / read-only) of attributes
 - field names
 - related help text
 - ordering, grouping and layout
- how values for attributes are obtained (using Configuration Templates):
 - fixed / default values
 - derived from data in the system; optionally combined with input from users or Device Model events using pre-defined macros (see: *Macros*)

Field Display Policies are applied to different roles using Menu Layouts and Landing Pages. Configuration Templates are applied to different roles using Menu Layouts, Landing Pages and pre-defined workflows.

The high level process that an administrator will follow is as follows:

- 1. Decide how an existing user input form should be customized. This involves an examination of the input form to identify field name, visibility, order and default values.
- 2. Determine the user who requires a modified input form.
- 3. Identify the User Role and Menu Layout associated with the relevant user.
- 4. If the menu item to be customized shows a Field Display Policy and Configuration Template associated with the item, clone these to start their customization. There is a unique constraint on the name of the clone per hierarchy level, so the same name as the original can be used on another hierarchy, but a new name is needed at the same hierarchy.
- 5. Create, or modify the cloned Field Display Policy and Configuration Template according to identified requirements to create new instances of these. Note the uniqueness constrains per hierarchy on the names of the clones.

6. Associate the newly created Field Display Policy and Configuration Template to the menu item in the user's Menu Layout as specified in the User Role. The Menu Layout may be created as a new Menu Layout that is only available at a specific hierarchy.

4.2. GUI Customization

4.2.1. Field Display Policies

Field Display Policies are applied to certain item types in order to modify the default form that is displayed when these items are created or accessed.

With Field Display Policies, the fields on an item detail form can be grouped, disabled, and on-line help text can be added for a field. A field can be provided with a new label and its position on the form can be moved up or down.

More than one Field Display Policy can apply to a particular item type so that the selection of a particular policy will present another view of the form.

A Field Display Policy for an item type can be applied from a Menu Layout by selecting and associating it with the item on the Menu Layout. The Menu Layout is then selected to be part of a user Role so that users who have this role and log in will be able to have the item displayed according to the relevant Field Display Policy.

For example, a system may have users at Provider, Customer and Site administration hierarchy levels - all of whom may access the same items, but perhaps some item fields need to be hidden for administration users at a certain level. Field Display Policies can then be made that are applied to the Menu Layout associated with the administration users at these levels.

A quick way to add a Field Display Policy is to clone an existing Field Display Policy, modify it as required and then to select it for the model on a user's menu layout. In this way a user's interface can be modified from the point of user access to the model on the menu.

There is a unique constraint on the name of the Field Display Policy per hierarchy level. The same name can be used on another hierarchy, but a new name is needed at the same hierarchy.

If a Field Display Policy is called default, it will apply to a model by default.

Note: The list view column header will also show the field title from the Field Display Policy if the field belongs to the list of summary attributes.

Related Topics

- Multi-vendor Subscriber Field Display Policy in the Core Feature Guide
- · Add or Edit a Field Display Policy in the Core Feature Guide

4.2.2. Create a Field Display Policy

A Field Display Policy can be added to any of Data models, Relations and Views to modify the default form that is available for the item.

- 1. Choose the relevant hierarchy level.
- 2. Click Add from Field Display Policies.
- 3. Enter the **Name** and and optionally a **Description** for the Field Display Policy. If the name is 'default', the Field Display Policy will apply to the target model type by default.
- 4. Select or verify the model reference for the **Target Model Type**.
- 5. Click '+' adjacent to **Groups** and add a group **Title**. All the fields of the display policy should belong to a Group. If a group displays as a tab on the Admin Portal, the Title is the tab title.
 - Select the **Display as Fieldset** check box to show the group **Title** as a group header on the Admin Portal and without tabs, or as a group title on a tab called **Base** if more than one group has this check box enabled.
 - Enter a numeric value for Number of Columns if the fields should show in columns.
- 6. On the Fields transfer boxes of the Group, select the required target model type fields from the Available box and add them to the Selected box. The available fields include fields from all versions of the schema of the target model type. Refer to the Rules When Creating a Field Display Policy topic for the caveats that apply when selecting the fields.
- 7. For each selected field in a **Selected** transfer box, its attributes can be configured in the **Field Overrides** group:
 - Field Select the field to which the attributes apply.
 - Title Select the label text to be shown for the attribute.
 - Help Text Enter text to display as the field on-line help and form tool tip for the attribute. If no text is added, the model attribute description is shown.
 - Disabled select the check box if the field should show as disabled.
 - Input Type The default display of the input field can be selected. For details, refer to the Field Display Policy Input Reference topic.
- 8. Click **Save** on the button bar to save the Field Display Policy.

The created Field Display Policy is available to be applied to the model by using it in a Menu Layout.

4.2.3. Rules When Creating a Field Display Policy

When creating groups and selecting the field transfer boxes of a group, a number of rules apply.

Regarding notation: if the fields belong to objects or arrays, the names in the transfer boxes are shown in dot notation. Refer to the target model type on-line help field reference to distinguish object types from array types.

To understand the rules below, consider a selected Target Model Type with the fields as listed below. Where the name starts with "A", the field is an array and where it starts with an "O" it is an object. The values "x", "y", "z" are also objects. The field "F" is neither object or array.

A, A.x, A.x.b, A.x.c, A.x.d, A.y.r, A.y.s, A.y.t

- F
- O, O.v, O.z, O.z.a, O.z.b, O.w.d

The following inclusion rules apply:

- If a parent object or array field is included, the parent and all its children will be displayed in the GUI. For example, if O.z is selected, O.z is saved as the fields and the GUI will display O.z and also inner fields O.z.a and O.z.b.
- If a specific selection and order of child elements are required, select these child elements and order them. For example, if O.w.d, O.z.b, F are selected, these three fields are saved in that order in the FDP group fields and the GUI shows only the inner field O.w.d, followed by the inner field O.z.b and lastly the field F.
- Inclusion of child fields in a group without the inclusion of the parent fields will display these child fields
 at the root level of the form. For example, if O.w.d, O.z.b are selected, these fields are saved as is in
 the FDP group fields list and only the inner fields O.w.d and O.w.b are shown in the GUI.
- Array children fields without their parent fields will be ignored by the GUI. Therefore, if the child fields of an array field are selected, the parent field should also be selected. For example, if A.y.s, A.y.t are selected, A and A.y should be selected.
- · Array fields may not be split into different groups.
- The parents of fields cannot be in one group and its children in another. For example, O.z cannot be in Group 1 if O.z.a, O.z.b and O.w.d are in Group 2.
- Fields of the same object and members of the same array type cannot belong to more than one group. For example:
 - If A.y.s is selected for Group 1, then A.y.t cannot be selected for Group 2.
 - If O.z.a is selected for Group 1, then O.z.b cannot be selected for Group 2
- You can split the first level children of object fields into different groups. For example:
 - O.v can be in Group 1 while O.z is in Group 2.
 - For second level children: O.z.a can be in Group 1 and O.w.d can be in Group 2.
- To hide a field, do not move it to a Selected box. For example, to hide O.z.b, select O.z.a, O.w.d.

To order fields in a group, arrange them in the Selected box. Use the **Move Up** and the **Move Down** buttons under the box.

The following ordering rule applies:

The ordering of child fields and their parents depend on the presence of siblings, other parents and children. If a child is selected in a group and not its parent, but a sibling of that parent is selected, then the sibling's order will affect the order of the fields.

The logic of order resolution starts from parents to children, according to the rules below.

For example, we select fields in this order in Group 1:

C.z, A.x.b, A.x.c, B, A.y, A.x, C, C.w

Result:

- Parent fields on their own are considered first, hence our initial order is B, C.
- However, parent A is not selected; only the children. We determine where A was mentioned. In this
 case the children of parent field A were mentioned before the parent fields B or C. Hence children of A
 will eventually be ordered before B and C.

- Next we consider the selected first level child fields: C.z, A.y, A.x, C.w. The order becomes: A.y, A.x, B, C, C.z, C.w
- We now move down the levels: A.x.b, A.x.c.

Thus the final display order will be:

A.y, A.x, A.x.b, A.x.c, B, C.z, C.w

Further examples below illustrate the presence of parents, siblings and children on the selected order.

• We add fields C.w, A, C, B, A.x, A.y.

Result: The order is: A, A.x, A.y, C, C.w, B.

We add fields A.x.b, A.x.c, A.y, A, B

Result: The order is: A, A.x, A.x.b, A.x.c, A.y, B.

Note that A.x was added and that A.y is placed after A.x, since the children were ordered before A.y while A.x was never selected.

Related Topics

· Field Display Policies in the Core Feature Guide

4.2.4. FieldDisplayPolicy Field Reference

Title	Field Name	Description	
Name *	name	The name that is given to the Field Display Policy.	
Description	description	A description for the Field Display Policy instance.	
Target Model Type *	target_model_type	The target model type to which the Field Display Policy applies.	
Groups	groups	The groups that describe groupings of attributes that are displayed together on the user interface.	
Title *	title	The name of a specific group of attributes.	
Display as Fieldset	display_as_fieldset	Render this group as a fieldset in the form.	
Number of Columns	num_cols	The number of columns of fields.	
Policy *	policy	The specific policy application to attributes of the target model type of the Field Display Policy.	

4.2.5. Clone a Field Display Policy

- 1. Login as provider administrator or higher.
- 2. Choose the desired hierarchy.
- 3. Choose Customizations > Field Display Policies to show the list of existing Field Display Policies.
- 4. Click on the field display policy that you want to clone.
- 5. Choose Actions > Clone.

- 6. Update the necessary fields for the cloned Field Display Policy. Refer to "Rules When Creating a Field Display Policy" for more information.
- 7. Click Save.

The cloned Field Display Policy is available to be applied to the item by selecting it in a Menu Layout that is available to a Role.

4.2.6. Field Display Policy Input Reference

Input Type	Can apply to Data Type
Default	
Multiselect	Array
Radio button	String - choices
Sequence	Array
Transferbox	Array

Sequence is a list of drop-down boxes created to allow for the selection of an item in the array: one is selected from each displayed drop-down list.

Transferbox is a side-by-side Available and Selected list boxes with controls to select and unselect items.


4.2.7. Example Field Display Policy Clone

The following example shows the **System User** interface before and after a cloned Field Display Policy has been modified and applied to an item on a Menu Layout change.

The table below shows the changed original and new order on the design form of the Field Display Policy so that all the mandatory fields display at the top of the item form.

Field Name	Orig. Order	New Order
User Name	1	1
First Name	2	4
Last Name	3	5
Email Address	4	2
Password	5	6
Repeat Password	6	7
Role	7	3
User Authorization Method	8	8

The screenshots show the example original and changed forms.



35

4.2.8. Configuration Templates

Configuration templates are used to define values for attributes of any model. The values can be fixed values or existing macros visible from the hierarchy context where the configuration template is applied. The templates provide a useful way to define default values for items that are exposed in the Admin Portal (visible, invisible or read-only). They also provide a mechanism to map data from data input via the Admin Portal or device model events to other models or Provisioning Workflows in the system.

One may want to hide attributes of a model while setting them to a specific fixed value (for example a hard-coded setting); or one may wish to derive the value based on a macro (for example, look up the value based on data in the system).

Another example is a model such as the Quick Add Subscriber that limits the user input to a few fields, whilst deriving the value of other hidden attributes from various Configuration Templates that are each applied to different underlying models that make up a Subscriber (for example, Voicemail account settings, conference account settings, phone, line, device profile settings, and so on).

When an instance of the model is added or updated, the Configuration Template that has been enabled for the model applies. For array elements of data models, a list and a variable can be specified to be looped through so that a value is applied to each element in the model array.

More than one Configuration Template can be created for a model. These can then be used as needed. Configuration Templates can also be applied to models in the design of for example Provisioning Workflows.

A Menu Layout that can be associated with a user role can also apply a Configuration Template to a model that is selected as a menu item.

For administrators at Provider Administrator level or higher, a quick way to create a Configuration Template would be to open a similar template from for example the **Configuration Templates** menu and to customize a clone of it.

Administrators at levels above the Site Administrator can also customize these templates, including Field Display Policies.

Note:

• When modifying Configuration Templates via the Admin Portal, numerical values need to be entered using the fn.as_int function, for example:

```
{{ fn.as_int 14 }}
```

• In a multi-cluster environment, Configuration Templates that result in device model drop-down lists on the Admin Portal may contain duplicates. Any duplicated item can be selected by the user.

4.2.9. Create a Configuration Template

- 1. Choose the hierarchy level at which you want to create a Configuration Template.
- 2. From the **Configuration Templates** list view, clone the required template.
- 3. Enter the Name (mandatory field) and Description, and verify the Target Model Type.
- 4. Use the **Custom feature usage identifier** array list input to add one or more values that can then for example be used in GUI Rules macros to filter choices in drop lists, for example by QAS and SAP below:

```
{# data.ConfigurationTemplate.name /
    target_model_type:device/cucm/User,feature_usage:QAS #}

{# data.ConfigurationTemplate.name /
    target_model_type:device/cucm/User,feature_usage:SAP #}
```

Note: Only add or modify the feature usage details for *custom features* which you add to the system. Changing the feature usage on Configuration Templates which are shipped with the product may have unintended behaviour changes for the standard set of features included with the product.

- 5. If the Configuration Template will be used along with other Configuration Templates that apply to the same **Target Model Type** in a Provisioning Workflow, select the **Merge Strategy** to be applied when these Configuration Templates are merged in the workflow:
 - Additive if the Data Type of the Target Model is an array, the Configuration Template will add an
 array item to any existing array.
 - Replace if the Data Type of the Target Model is an array, the Configuration Template will replace
 the array item of any existing array.
- 6. If required for model attributes that are arrays, add Foreach Elements by clicking + (Add) for each:
 - a. Enter a **Property** that is the model array attribute to which the entry applies.
 - b. Enter a Macro List to loop over. A macro list opens with {# and closes with #}.
 - c. Enter a Context Variable name to store the current loop value of the macro list.

The **Context Variable** is referenced as a macro with the *cft* prefix in the Configuration Template value for the array attribute, so that for each instance in the list loop, an array entry is created when the template is applied. For example: {{cft.MyContextVar.name}} Configuration Templates that are part of Provisioning Workflows can reference spreadsheet column values using the input syntax: {{input.[entity attribute]}}, for example {{input.username}}.

- 7. In the **Target Model Type** section, enter (default) values for those displayed attributes that these should be applied to when the template is used in conjunction with the target model. If the user has access to macros, the values can be macros to determine values.
- 8. Click **Save** on the button bar to create and save the Configuration Template.

The created Configuration Template is available to be applied to the model by for example using it in a Menu Layout or Provisioning Workflow.

4.2.10. Configuration Templates for Array Updates

When creating Configuration Templates for any of the models in the **Model Type** column below, it is not necessary to also set changed and existing values for *every* array item in the **Array Field** column.

Only values for the *changed* items are required. The attribute in the **Identifying Attribute** column will be used to maintain the existing array item values.

Model Type	Array Field	Identifying Attribute
RemoteDestinationProfile	lines.line	dirn
RemoteDestinationProfile	lines.line.associatedEndusers.enduser	userld
CtiRoutePoint	lines.line	dirn
CtiRoutePoint	lines.line.associatedEndusers.enduser	userld
Phone	lines.line	dirn
Phone	lines.line.associatedEndusers.enduser	userld
GatewaySccpEndpoints	endpoint.lines.line	dirn
GatewaySccpEndpoints	endpoint.lines.line.associatedEndusers.enduser	userld
GatewayEndpointAnalogAccess	endpoint.lines.line	dirn
GatewayEndpointAnalogAccess	endpoint.lines.line.associatedEndusers.enduser	userld
DeviceProfile	lines.line	dirn
DeviceProfile	lines.line.associatedEndusers.enduser	userld

4.2.11. Events

Events execute Provisioning Workflows in response to a trigger. The trigger is an operation that is carried out on a selected model. The available actions for a selected model define the list of available operations.

Event instances to trigger are searched for as follows: the lower of:

- the transaction hierarchy (in other words the transaction "breadcrumb")
- the triggering resource hierarchy

When an Event instance is defined, the following values are specified:

- · Workflow the created Provisioning Workflow is selected.
- Active if the Event is to be enabled, it is set to be active. This means events can be created without being active.
- Model Type This is a part of the transaction. Operations on Model Types define the transaction.
- Operation the available operations depend on the selected Model Type.
- Phase the event can take place before or after the defined transaction. For example, if the Create Operation is available for the Model Type and the Phase is Pre Execution, then the event workflow is run *before* the Create Operation.
- Synchronous if enabled, the transaction is only carried out if the HTTP response from the HTTP request in the workflow shows the request was received, in other words the response is of the format

HTTP 2xx. If the Event is not set to be Synchronous, in other words it is asynchronous, the transaction is carried out regardless of the HTTP response.

Warning: Always enable events as Synchronous, unless there is a good reason to set an event as asynchronous. Failed asynchronous events do not roll back the triggering transaction and can lead to unexpected issues.

A hierarchy context of the selected model is available to a Workflow in the case of events. In the case where a model allows for a Move operation and a Post Execution Phase is specified, this hierarchy value would be changed to the new hierarchy.

Consider for example the following transaction context data:

```
Pre event hierarchy: 5404f304c8e69d774458660e
Post event hierarchy: 5404f711c8e69d774458a92a
device/cucm/User Pre Asynchronous move:
Step 0 - Executing workflow (testEVPWF) with the following context data:
    "input": {
        "device_pkid": "5404f345c8e69d7744586676"
    "trigger": {
        "model_type": "device/cucm/User",
        "phase": "preexecution",
        "operation": "move",
        "trigger_model_type": "data/Event",
        "name": "testEV_cucmUser_Pre_async_move"
    },
    "resource_meta": {
        "model_type": "device/cucm/User",
        "pkid": "5405ba26c8e69d77445b8769",
        "hierarchy": "5404f304c8e69d774458660e",
        "device_pkid": "5404f345c8e69d7744586676"
    },
device/cucm/User Post Asynchronous move:
Step 0 - Executing workflow (testEVPWF) with the following context data:
 {
    "input": {
        "device_pkid": "5404f345c8e69d7744586676"
    "trigger": {
        "model_type": "device/cucm/User",
        "phase": "postexecution",
        "operation": "move",
        "trigger_model_type": "data/Event",
        "name": "testEV_cucmUser_Post_async_move"
    "resource_meta": {
        "model_type": "device/cucm/User",
```

(continues on next page)

(continued from previous page)

The Provisioning Workflow is triggered from the lower of: the transaction hierarchy (eg. breadcrumb) and the hierarchy where the event instance is located.

To override this hierarchy in order that the workflow is run in the target hierarchy, use the {{ resource_meta.hierarchy }} macro for the workflow context hierarchy.

For example:

```
"meta": {},
  "resources": [
        "meta": {
            "model_type": "data/ProvisioningWorkflow",
            "pkid": "53fde2d02afa4356c87e45c4",
            "schema_version": "0.3.9",
            "hierarchy": "sys",
            "tags": []
        },
         "data": {
            "name": "__post_event_test",
            "parameters": {
               "max_workers": "1",
               "parallel": "false"
            },
            "workflow": [
               {
                 "entity_type": "model",
                 "hierarchy": "{{ resource_meta.hierarchy }}",
                 "entity": "data/Countries",
                 "method": "refresh",
                 "advanced_find_options": [
                          "model_attribute": "iso_country_code",
                          "mapped value": "USA"
                   ],
                 "advanced_find_search_direction": "full_tree"
               }
            ]
         }
    }
 ]
}
```

4.2.12. GUI Rules

For model forms, a set of rules can be defined that specify:

- 1. An initial state of the model form.
- A change in its behavior and values on it in accordance with data and events that take place on the form.

This set of rules is defined in a GUI Rule model and it applies to a selected model's form when it is used.

GUI Rules can, for example, be used to hide or show input controls, to enter values or to enable controls in accordance with change or input on the form.

When a GUI Rule is created, the design form applies to the specified model. Field Specific rules can be specified as well as Events on fields. Events are associated with Actions on fields. In other words, if a certain event takes place in a field, actions can be carried out on other fields.

The actions of an event depend on conditions. More than one condition can be specified.

Note:

- In the case where a GUI Rule is applied to a Device Model, the attributes of all device versions are available for events and actions. The GUI drop-down lists for GUI Rules would list the union of device attributes. In other words, since all device versions are supported by GUI Rules, a GUI Rule can be defined to support all these device versions. If a specific form on the GUI does not display a particular field, any related GUI Rule will not be applied to the form.
- An event GUI Rule at a higher hierarchy level will precede a Field Specific GUI Rule at a lower hierarchy level, but for Dropdown Filters, we create event GUI Rules at the lower hierarchy level, thereby avoiding this precedence.

4.2.13. GUI Rule for the Target Model of a Configuration Template

If a GUI Rule is created for a target model referenced in a Configuration Template, then the GUI Rule is applied to this target model type referenced in the Configuration Template.

For example, a GUI Rule called <code>ConfigurationTemplateOverride</code> is available for the model <code>device/ios/Script</code> (which is a target in a Configuration Template for a Script - refer to the topic on Scripts). This GUI Rule has a Field Specific rule for the field <code>expect_script</code> (originally of type String) and sets its type to <code>multi_line</code>.

GUI Rules called ConfigurationTemplateOverride exist for the following models:

- device/ios/Script
- device/pgw/Script

For example:

```
"meta": {
    "model_type": "data/GUIRule",
    "schema_version": "0.4.9",
    "hierarchy": "sys",
    "tags": [
        "base",
```

(continues on next page)

(continued from previous page)

```
"core"
    ]
},
"data": {
    "field_specific": [
        {
             "field": "expect_script",
             "property": "type",
             "value": "multiline"
        },
        {
            "field": "expect_script",
             "property": "scrollbars",
             "value": "true"
        }
    ],
    "type": "device/ios/Script",
    "name": "ConfigurationTemplateOverride"
}
```

4.2.14. Relations

Relations do not store data on the system. They relate groups of resource types such as device models and data models.

The purpose of a Relation is to provide a model type that can group together related models and then carry out operations on them. Model types are related by joining them similarly to a SQL "left join". One or more fields can be specified as foreign keys.

A relation of relations is not supported.

A Relation will show all the attributes of its model types by default. Even fields specified as foreign keys will appear for each of their respective model types. Unwanted attributes are hidden using a Field Display Policy, and default values of hidden attributes can be assigned using a Configuration Template.

Operations are added to Relations. Operations with associated workflows will execute their custom workflow. *Add*, *modify* and *delete* operations without workflows will execute a dynamic workflow that simply adds, modifies, or deletes all related model instances. However, if a Relation for example contains *shared* Phones or Lines (as the Subscriber relation), then these related model instances are not deleted.

4.2.15. Tags

During system customization and when creating dial plan models, Configuration Templates, and so on, a set of model instances can be grouped with one or more common tags. Such tagging is useful in order to find all customizations that have the same tag.

Tags can be added to an instance of a model. The tag value can be any string. (For designers: enabling the GUI Rules setting called **Show Metadata Information** for the model type will show the tags that have been added to the model instance on the model design form).

The same tag can for example be used with more than one model instance. A tag or a list of tags can be specified when a search is carried out in the user interface search box, for example tag is feature my feature name.

See also the Search Syntax topic in the Core Feature Guide.

The same tags can for example be added to a number of model instances so that they can then all be listed by carrying out a search for this tag. The search results list is then available to carry out common tasks on the list view such as export, packaging and deletion.

4.2.16. Add and Remove Tags

Tags allow you to search for all model instances with a common tag so that you can perform bulk operations on model instances sharing the tag.

This procedure adds and removes tags.

Prerequisites:

- · Your access profile should allow tagging on the model.
- You should have access to the model instance.

Perform the following steps:

- 1. Log in to the administrator interface.
- 2. Choose the hierarchy to which the model belongs.
- 3. Choose an instance of the model you wish to tag.
- 4. Click the Tag action; then:
 - To add a tag, type in a tag name.

Important:

- To ensure tags are searchable, use only lowercase letters in tag names.
- Tag names should not contain spaces.

You can add more than one tag to a model instance.

· To remove a tag:

To remove an existing tag name; that is, <tag_name>, type the following prefix to the existing tag name: __CLEAR_TAG__<tag_name>

To remove all tags, type ___CLEAR_ALL_TAGS__ as the tag value.

4.2.17. Create a View

A View is a model type that is used to provide an input form. A view instance does not store any data entered on its form on the system. Attributes and operations (workflows or tools) on these attributes can be defined.

Users with access to this model type for customization can manage views.

- 1. Choose the hierarchy level for the model.
- 2. Open the Views list view.
- 3. Click **Add** on the button bar to open the Views input form.
- 4. Enter a Name for the Attribute.

- 5. Click **Add** adjacent to Attribute Properties to expand the selection.
- 6. Enter one or more attributes (click **Add** as required to create other instances for the same attribute) where:
 - a. Name Used as reference target.
 - b. Friendly Name Optionally an alternative field label.
 - c. Description Optionally a documentation description of the attribute that also shows as a tool tip and on the on-line help page.
 - d. Data Type Choose from the drop-down-list. The selection modifies the available attribute properties for Array and Object data types. For a String data type, a number of options are available:
 - · Maximum Length.
 - · Version.
 - String Format The selected String Format acts as an input filter on the string data in the data model.
 - Is Password? if the data type will be used to enter a password. In this case the value will be masked on forms.
 - · Is Mandatory? or Is Read-Only?.

Note: For fields that are marked read-only, these require an additional GUI Rule to provide this functionality. Since views are not designed to be updated, data in such fields would be for informational purposes.

- Validation Regular Expression that the string should meet. For example, "[a-z]{4}" without quotes specifies 4 characters in the range a to z in small case.
- · Default Value.

For example, the format "Date ("YYYY-MM-DD")" requires delimited numeric text input data in the specified format and input fails if the format does not meet the format).

If the selected String Format is URI, additional controls are available to select a data-, domainor device model (Target) attribute (Target Field) to be accessible in the created data model as a drop-down list of the Target Field attributes available in the Target model.

For data type: Anything, Boolean, Integer, Null, Number, choose if the attribute Is Mandatory? or Is Read-Only? or has a Default Value. For each required input control to be available on the form, add an **Attribute Properties** entry of the required **Data Type**.

- Click Add adjacent to Choices and enter a Value and Title as required. Click Add to open up multiple instances if required.
- 8. Click **Add** adjacent to Workflows to expand the selection, and enter the required Operation and Workflow parameters. Click **Add** as required to open additional instances of the required values.
- 9. Click **Save** on the button bar when complete to save the created View.

4.3. Theme Customization

4.3.1. Less files and Theme Customization

After downloading and extracting a theme into a directory, the contents shows the following directories and files:

```
.
+-- build_dependencies
+-- img
+-- skin.css
+-- skin.less
+-- variables.css
+-- variables.less
```

Three files are available for theme customization:

- variables.less: custom variables overriding variables set elsewhere. To be compiled as variables.css when done.
- skin.less: main customization file to be compiled to skin.css when done.

Custom images for login page backgrounds and logos are added to the img directory.

The override hierarchy of variables and theme settings is seen as the first lines of skin.less as @import instructions, for example:

```
// Loads default variables
@import (optional) "build_dependencies/themes/minimal/variables.less";
@import (optional) "../minimal/variables.less";
// Overrides some default variables
@import "variables.less";
@import (optional) "build_dependencies/css/coreAdministratorStyles.less";
@import (optional) "../../css/coreAdministratorStyles.less";
```

Imports lower down on the list override those imports higher up on the list. The (optional) parameter indicates the import is ignored if the file is not available.

It is not advised to remove any references to files in the build_dependencies directory.

Customizing variables.less

Variables are used in skin.less and in other .less files in the sub-directories of the build_dependencies directory. Use variables.less to override any of these existing variable values. New variables can also be added if required and used in skin.less.

Existing variables and values are in build_dependencies/themes/minimal/variables.less. The variable names have self-explanatory names and are grouped into Admin Portal categories, such as login page, landing page or colors.

For example, in the default theme, show the following in variables.less:

```
@currentYear: ~`new Date().getFullYear()`;
@copyrightNotice: '\00A9 @{currentYear} VOSS. All Rights Reserved';
```

(continues on next page)

(continued from previous page)

```
@loginLogoWidth: 161px;
@loginLogoHeight: 51px;
```


These variables are used in skin.less and determine:

• the footer copyright notice, for example, in skin.css, the content property:

```
body.login_page:after {
  position: fixed;
  bottom: 0;
  content: '\00A9 2017 VOSS. All Rights Reserved';
  left: 0;
  color: #eeca;
  z-index: 1;
  background-repeat: no-repeat;
  background-position: left;
}
```

• the landing page logo image size HTML attributes:

```
<img style="user-select: none;"
src="http://localhost/www/themes/default/img/login_logo.png"
width="161"
height="51">
```



Customizing skin.less

Customization is carried out by overriding the entries in the imported .less files present in the sub-directories of build_dependencies. In the compiled .css file, the override theme changes will then follow the original CSS entries.


It is recommended that the browser developer tools be enabled in order to identify matching HTML properties of portions of the Admin Portal, as well as the associated Admin Portal styling in the skin.css file.

For example, consider an entry in the default theme skin.less under the heading Navbar. The Navbar theme settings apply to the navigation headers of the application: the top and side menu bars. For more details on the navbar component, see: Navbar.

```
.navbar .navbar-inner {
  background: @mainBackgroundColor;
}
```

Here, the background color of the horizontal navbar is modified. the value of <code>@mainBackgroundColor</code> is defined earlier as #3280d2.

The application of this override to the theme is shown by inspection in the browser developer tools:



In the compiled skin.css file, the update in the snippet from the less file above will follow the main definition:

```
.navbar .navbar-inner {
  background: #3280d2;
}
```

The main definition shows all the values that apply to navbar-inner. The value of background-color is overridden.

```
.navbar-inner {
   min-height: 40px;
   padding-right: 20px;
   padding-left: 20px;
   background-color: #fafafa;
   background-image: -moz-linear-gradient(top, #fff, #f2f2f2);
   background-image: -webkit-gradient(linear, 0 0, 0 100%,
     from (#fff), to (#f2f2f2));
   background-image: -webkit-linear-gradient(top, #fff, #f2f2f2);
   background-image: -o-linear-gradient(top, #fff, #f2f2f2);
   background-image: linear-gradient(to bottom, #fff, #f2f2f2);
   background-repeat: repeat-x;
   border: 1px solid #d4d4d4;
   -webkit-border-radius: 4px;
   -moz-border-radius: 4px;
   border-radius: 4px;
   filter: progid:DXImageTransform.Microsoft.gradient(
     startColorstr='#ffffffff',
     endColorstr='#fff2f2f2',GradientType=0);
   -webkit-box-shadow: 0 1px 4px rgba(0,0,0,0.065);
   -moz-box-shadow: 0 1px 4px rgba(0,0,0,0.065);
   box-shadow: 0 1px 4px rgba(0,0,0,0.065)
```

Similarly, other values in the CSS file for .navbar-inner can be overridden.

Another example: if the alert notification pop-up style (for example with timeout notifications) should also be customized to match the custom style, the following style can be added - with the suitable style colors:

```
.alert-info {
  color: #31708f;
  background-color: #d9edf7;
  border-color: #bce8f1;
}
```


4.3.2. Theme Banner Customization

For Less files in general and how to update, compile and upload your theme, see:

- · Download and Update a Theme on the Legacy Admin Portal
- · Less files and Theme Customization

To customize the look and feel of the banner text managed from the theme (see *Set the Login Page Theme and Text on the Legacy Admin Portal*), inspect the styles in skin.css that apply to the theme Site Title and Banner Text. Both are marked up in HTML as <h1>:

- Site Title: .login_page h1
- Banner Text: h1.banner



If a style is defined for the Site Title and there is no style override for the Banner Text, then the Site Title style applies to the Banner Text. More generally, styles for h1 apply.

For example, unless the h1.banner customization includes values for font-size and color, the values of the variables in variables.less: @loginBannerFontSize and @loginBannerFontColor will apply to the banner text.

In skin.less, Banner Text style customization can for example include the following attributes,

```
h1.banner {
    color:
    font-family:
    font-size:
    font-weight:
    line-height:
    margin:
    margin-left: [use negative value to show text outside login form box] - see below]
    text-align:
    text-shadow:
    width:
}
```

For margin-left, if you wish to center the banner, the negative margin and total width will have to be calculated. The margin-left value should be the negative of:

```
(banner width - login form width) /2
```

For example, if the username/password fields are 400px wide (determine this with the browser developer tools), and the banner width is set to 800px, then the margin-left of the banner should be:

```
(800px-400px)/2 = -200px
```

Therefore, the skin.less file will contain:

```
h1.banner{
  width: 800px;
  margin-left: -200px;
  ...
}
```

4.3.3. Privacy Policy Menu Items

In order to comply with General Data Protection Regulation (GDPR) requirements, VOSS-4-UC provides the means to manage privacy policy notices on the user interface.

By default, high level system administrators above the Provider level hierarchy can manage privacy policy references that are available on user menus. These administrators can provide the required access to the data/PrivacyPolicy data model and add menus to lower level administrators if required.

Privacy policy references can be set up for each hierarchy. If one is not added to a specific hierarchy, the one at the next higher hierarchy applies.

When a privacy policy applies to a user hierarchy:

- On the Admin Portal, a privacy policy menu item is added to the bottom of the user's menu. The title of the menu item is the name of the created policy.
- On the Self-service GUI (if available), a side button bar menu item is added. The title of the menu item is **Privacy Policy**.

When selecting the menu item, the link URL of the policy opens on a new browser tab.

Note:

- For the Admin Portal, the Privacy Policy menu item is not visible from a menu layout and cannot be managed from Menu layouts.
- Login page privacy policy links are managed from Themes. Refer to Set the Login Page Theme and Text on the Legacy Admin Portal.

4.3.4. Manage Privacy Policy Menu Items

- 1. Log in as an administrator with the required privacy policy management permissions and menu access.
- Choose the menu item, for example by default, Privacy Policy Configuration. The list view shows privacy policy names and links at various hierarchies in the system. Privacy policies can then be added, modified and deleted.
- 3. To add a privacy policy, navigate to the hierarchy at which the privacy policy should be added and click **Add**.
- 4. Add a Name, Privacy Policy URL and click Save. Note that this name becomes the menu item name.

On the Admin Portal, a privacy policy menu item is added to the bottom of the user's menu - for users at the specified hierarchy or lower and without a privacy policy on their own hierarchy. On the Self-service GUI, a side button bar menu item is added.



4.3.5. Download and Update a Theme on the Legacy Admin Portal

- 1. Choose the hierarchy level at which the theme will be applied. Note that themes can only be customized by a Provider Administrator (or higher).
- 2. Choose Role Management > Themes to open the Themes list view.
- 3. Click the theme that you want to download.
- 4. Click **Action > Download** on the button bar to download the theme. The exported file is a .zip archive with the name of the theme. The archive contains a folder with the theme name and files called skin.css and skin.less in it.
- 5. Refer to the recommended practice to edit the Less file at the end of this topic, otherwise save the file and open the CSS file in a text editor.
 - Headers are clearly marked and apply to design areas within the Admin Portal.
 - · Colors, sizes, fonts, images, and so on, can all be overwritten with the required formats.
 - Images must be identified with the correct file path name. Preferably, do not use '/' preceding the path name; rather use relative paths, in other words a path relative to the CSS file location. For example, if your created an image sub-folder called 'img', use 'img/myimage.png'. After upload, the image should be viewable when opening the URL: /www/themes/mytheme/img/myimage.png">http://chostname>/www/themes/mytheme/img/myimage.png
- 6. When editing is complete, make sure the directory folder name is the same as your theme name. Compress the folder and save the file with the theme name and a .zip file extension.

An error message will display on the user interface if the file does not have a valid file extension.

Note that any files or folders inside the zip file archive that start with a '.' character will be silently discarded when unzipping the theme. For example, if the zip archive contains any files named ._.DS_Store or .directory, they will be ignored.

Important: If customization is done on MS Windows, check that no desktop.ini files reside in the

directory tree of the theme before compressing it.

7. Choose **Themes**:

- a. For an update, choose the theme name and click **Browse** adjacent to **Import File** and then open the same theme name. Optionally select the **Backup Enabled** check box to create a backup of the current theme on the server. Click **Save** to complete the import process.
 - If a theme update does not require an updated CSS in a zip file but only updates the text of the theme, then no file upload is required. For information about the other fields on this form, refer to the topic on adding a theme.
- b. To delete a theme, choose it from the list and click **Action > Delete**.

The preferred way to edit a theme is to edit and compile the Less files. Refer to the "Less files and Theme Customization" topic in the "Advanced Configuration Guide".

- All changes that are made directly in the CSS files will have to be manually carried over after each changes in the Less files.
- · Edit the Less files and compile them to get the new CSS files.
- The aim with Less is that a theme can be customized with the minimum of technical knowledge (as with for example Twitter Bootstrap [http://getbootstrap.com/customize/>].

For an introduction to Less, visit the official website [http://lesscss.org/]. To compile the Less theme, a Less compiler is required. The following list shows examples:

- Online [http://lesscss.org/usage/index.html#online-less-compilers>]
- on your desktop [http://lesscss.org/usage/index.html#guis-for-less]
- IDE [http://lesscss.org/usage/index.html#editors-and-plugins]

4.3.6. Add a Theme on the Legacy Admin Portal

- 1. Prepare the theme file:
 - a. The recommended procedure is to use an export of an exiting theme as a baseline and update it with a new name, images and colours as required. Refer to *Download and Update a Theme on the Legacy Admin Portal* for details.
 - b. Create a folder with the required name of the theme and un-zip the exported theme in it, maintaining directory structure.
 - The name of the folder must be the same as the intended theme name (only alphanumeric characters or underscore can be used, with no spaces or special characters).
 - c. Add any CSS overrides to the file. Note that only the definitions as shown in the export of a provided CSS file skin.css can be modified.
 - d. Add required image files in this folder (if any).

Important: If customization is done on MS Windows, check that no desktop.ini files reside in the directory tree of the theme before compressing it.

- e. Create a .zip archive file with the same filename as the folder.
- 2. Add the theme to the system:

- a. Choose the hierarchy level at which the theme will be created.
- b. Choose **Role Management > Themes** to open the **Themes** list view.
- c. Click **Add** on the button bar to open the **Themes** input form. Note that themes can only be customized by a Provider Administrator (or higher).
- d. Enter the **Theme Name** (same as the file name created above).
- e. Enter Navbar Text if needed. This will show on the navigation bar next to the logo.
- f. Enter an appropriate **Site Title** if required. The site title entered here is the text displayed in the browser tab.
- g. Click the **Browse** button to import the created theme zip file. Wait until the system displays the file chosen in the **Import File** field.
- h. If the theme must also apply to the login page, select the **Use this Theme to style Login page** check box.
- i. To set login banner text and notices on the login page, refer to *Set the Login Page Theme and Text on the Legacy Admin Portal*. The **Use this Theme to style Login page** check box does not have to be selected for banner text to show.
- j. If you want to hide the theme from lower level hierarchies, select the **Hide from Lower Hierarchies** check box. Users logged in at lower level hierarchies will not be able to see that particular theme on the **Themes** list view screen.
- k. For details on the **Theme Customization** tab controls, refer to *Create a Theme in the Admin and Business Admin Portal*.

Note: If any details are added on this tab, all fields should be provided with input.

- Choose Interface to which the theme applies from the drop down. By default the theme applies
 to the Administration interface.
- m. Click **Save** on the button bar when complete.

Note: Do not leave the screen until the processing of the theme completes and theme list is refreshed. This can take a few minutes depending on details and complexity of theme uploaded.

4.3.7. Create a Theme in the Admin and Business Admin Portal

The **Themes** interface in the Admin and Business Admin Portal can be used to create a theme that applies to the Business Admin Portal as well as the VOSS-4-UC Admin Portal.

Note:

- Since two themes are compiled when saving a new theme on the Business Admin Portal, this takes slightly longer than theme compilation on the VOSS-4-UC Admin Portal.
- Themes created in the Admin Portal and Business Admin Portal:
 - cannot be exported in full
 - require the use of the Legacy Admin Portal to include login page text and to define a non-admin Interface.

Use the **Preview** button to preview the saved theme before it is applied to the user interface by assigning it to a user role.

Theme Details

Note: If the Admin Portal or Business Admin Portal Theme interface is to be used for full Admin Portal theme configuration, a Custom Admin Portal File should be uploaded.

Custom Admin Portal File:

- If a theme file is added:

the theme file will apply the Legacy Admin Portal, while the theme customization updates made in the **Branding** group of controls will *only* apply to the Admin Portal and Business Admin Portal, but may be overridden in the Legacy Admin Portal.

If no theme file is added:

the theme updates made in the **Branding** group of controls are applied to Legacy Admin Portal, Admin Portal and the Business Admin Portal. The **Custom Admin Portal File** upload control is then *not* available for theme modification.

Branding

Note: Color selection is optional: where no colors are selected, defaults apply.

- · Color selection:
 - Select a color using either the color picker control or by typing in the color hex value. The color picker control is only available on the Business Admin Portal theme interface.

Refer to:

- Legacy Admin Portal Theme Element Color Reference.
- * Administration Portal Theme Customization Color Reference
- · Image upload:
 - Note the file size and width x height pixel dimension size restrictions (shown on the context sensitive help) for images. A warning message will also show if selected images are too large.

The **Logo** image format must be PNG format. Other images can be PNG or JPEG.

- The Menu Background image does not apply to the VOSS-4-UC Admin Portal.

4.3.8. Legacy Admin Portal Theme Element Color Reference

Note: Color selection is optional: where no colors are selected, defaults apply.

The Legacy Admin Portal GUI Element variable below is a descriptive name of the Admin Portal and Business Admin Portal GUI element that will be affected by the Color variable, which corresponds with the color name on the Theme design form.

Element	Color	Theme GUI Branding tab
\$sidebarLogoBgColor	\$primaryColor	Primary Color
\$sidebarBgColor	\$primaryColor	Primary Color
\$topbarTextColor	\$primaryLightestColor	Very Light Primary Colour
\$topbarlconColor	\$primaryLightestColor	Very Light Primary Colour
\$submenuBgColor	\$primaryColor	Primary Color
\$darkSubmenuBgColor	\$primaryDarkColor	Dark Primary Colour
\$horizontalSubmenuBgColor	\$primaryColor	Primary Color
\$horizontalSubmenuitemHoverBgColor	\$primaryColor	Primary Color
\$horizontalSubmenuitemDarkHoverBgColor	\$primaryColor	Primary Color
\$menuitemActiveBgColor	\$accentColor	Accent Color
\$subMenuitemActiveTextColor	\$accentLightColor	Light Accent Color
\$subMenuitemActiveIconTextColor	\$accentLightColor	Light Accent Color
\$darkMenuitemActiveBgColor	\$accentColor	Accent Color
\$darksubMenuitemActiveTextColor	\$accentLightColor	Light Accent Color
\$darksubMenuitemActiveIconTextColor	\$accentLightColor	Light Accent Color

4.3.9. Administration Portal Theme Customization Color Reference

Note:

- Color selection on the **Branding** tab of a theme *always* affects the Admin and Business Admin Portal.
- Color selection on the **Branding** tab of a theme *only* affects the Legacy Admin Portal *if no theme file* is attached to the theme.

To edit and manage theme files:


Refer to Less files and Theme Customization in the Advanced Configuration Guide.

· Color selection is optional: where no colors are selected, defaults apply.

On the Legacy Admin Portal, consider the color selection on the **Theme Customisation** tab:





On the Admin Portal, consider the color selection on the **Branding** tab:




The screens below show how the branding colors of the theme appear in the Legacy, current and Business Admin Portal.


Legacy Admin Portal






Admin Portal







59

Business Admin Portal







4.3.10. Set the Login Page Theme and Text on the Legacy Admin Portal

- 1. Choose the hierarchy level in which the theme was created or to which the theme belongs.
- 2. Choose Role Management > Themes to open the Themes list view.
- 3. Click the required **Theme Name** that you want to use for the Login page.
- 4. On the Base tab, select the Use this Theme to style Login page check box.

If the check box is selected, and a theme with the same Interface already has the Login page check box selected, this will result in the disabling of the check box on the existing theme. There can only be one Interface-Login page combination on the system, so that any new themes or updates to existing themes may modify other themes on the system with the same Interface by disabling their Login page attributes. If no Interface is specified, the new login theme will also have its interface set to Administration.

5. On the Login Page Details tab, enter the required text in the Title field and Banner Text field. The text entered in the Title field will be displayed at the top of the Login page, above the logo. The text entered in the Banner Text field will be displayed at the bottom of the Login page, below the Log In button.

The banner text input box allows for multi-line input so that paragraphs can be created.

The maximum character length of the banner text is 2048 characters.

Banner text is displayed in the format that it is entered into the input box upon configuration. If cookie and security policy references are added, these show as links that open in new browser tabs.

- 6. In the **Banner Text** field, references to the cookie policy and privacy policy are added to the text as placeholders:
 - {{cookie_policy}}
 - {{privacy_policy}}

Input boxes are available on the Banner input form to add a caption and URL for each.

Although the cookie and privacy policy references are both optional, both their caption and URL fields become mandatory if they are used. The placeholder reference is then also required in the banner input box.

For suggested input on the use of cookies by VOSS-4-UC in the cookie policy text, see *VOSS-4-UC Cookie Policy*.

Note that if a browser has a blocker installed that prevents new tabs from opening, this will affect the functionality of the links in the login banner.

Privacy policy links can also be added to user menus. Refer to *Privacy Policy Menu Items* and *Manage Privacy Policy Menu Items*.

To customize the banner text style, refer to the topic on "Theme Banner Customization" in the "Advanced Configuration Guide".

7. Click **Save** on the button bar when complete to implement the selection.

The Login page theme can also be applied to the login page during the log in process. Do this by adding the URL parameter <code>theme=<theme-name></code> to the login request URL. This usage in the URL will apply and override any theme that is set as the login theme.

Note: For Self-service, if the theme value is set as login?theme=cisco_selfservice then the theme will revert to the Self-service theme that has been set as the default.

For example, when 2 themes are available in the system, XYZ and ABC and XYZ login page is set to be the default:

Legacy Admin GUI:

```
https://instance/login/-Login page will show use XYZ theme
https://instance/login/?theme=ABC - Login page will show use ABC theme
```

· New VOSS Admin Portal:

```
https://instance/portal/#/admin - Login page will show use XYZ theme https://instance/portal/#/login?targetAppMode=admin&theme=ABC - Login page will show use ABC theme
```

· Business Admin Portal:

4.3.11. VOSS-4-UC Cookie Policy

When formulating a cookie policy, customers should include details on the use of cookies by VOSS-4-UC. The text below provides details on the use of cookies in VOSS-4-UC that can be included in the policy:

```
VOSS-4-UC uses cookies for the following purposes:
Personalisation - we use cookies to store information about your most recent settings,
preferences and to personalize our website for you.
The cookies used for this purpose are:
hierarchyTreeSaveStateCookie
resourceTreeSaveSelectedCookie
resourceTreeSaveStateCookie
ace.settings
sso_login_url
Security - we use cookies as an element of the security measures used to protect
user accounts, including preventing fraudulent use of login credentials, and to
protect our website and services generally.
The cookies used for this purpose are:
* Administrator login:
 csrftoken
 sessionid
* Self-service login:
 csrftoken
 sessionid
 session
 rbacInfo
```

4.3.12. Default Business Admin Subscriber Profile

If you don't want the **Default** Subscriber Profile to appear as an option when adding a Subscriber, a sysadmin user *only* can delete it from the **Subscriber Profiles** list view.

4.4. Menu Customization

4.4.1. Menu Diff Tool

Note: This feature is available only in the VOSS-4-UC Admin Portal. It is not available in the Legacy Admin Portal.

System level (hcsadmin, entadmin) and provider administrators have access to the Menu Diff tool on the menu to allow for a side-by-side comparison and management of two selected menu layouts:

- **Source Menu**: a drop-down list of menu layouts from hierarchies at the administrator's hierarchy *and higher*.
- Target Menu: a drop-down list of menu layouts from hierarchies at the administrator's hierarchy and lower.

The side-by-side forms with the two selected menus can be expanded using the **Expand/Collapse** button. Menu differences are highlighted as follows:

- The same menu item in both menus but on a different menu path is highlighted.
- A menu item in one menu but not in the other menu is highlighted.

To update the target menu, drag and drop menu items from the source menu to a position in the target menu.

• Where a menu item is now in both menus, it is not highlighted anymore.

Note:

- All menu properties (e.g. Field Display Policy, model reference, and so on) are copied.
- If the menu item than is copied contains sub-menus, these are included.

Click Save to save changes in the target menu.

4.5. On-line Help

4.5.1. On-line Help Customization

Note: The customization to on-line help discussed here refers to the data in the data/GeneralHelp model.

The online help information that is available can include general and field-level information. This information can be added in the following ways:

- On the design input form of the model. In this way the creator of a model can include its on-line help information. Field-level help is also shown as a tool-tip pop-up in the instance input form of the model.
- In a Field Display Policy that applies to the model. In this way the default information on the model can be overridden if the Field Display Policy is applied to the model. A Field Display Policy can be associated with a model from its access in the Menu Layout.
- If write access to the data/GeneralHelp model is available, instances of this model can be marked as information to display on the on-line help for a model. This is done by adding Model Overwrite Details array instances to a data/GeneralHelp model instance.

Role-based access on models and model fields, as well as Field Display Policies for models can be used to customize a user's view of the available on-line help.

Instances of the data/GeneralHelp model created at a selected hierarchy level provide hierarchy-specific content. If the name of the instance of data/GeneralHelp at a hierarchy level is the *same* as that of an existing default instance, the default instance is replaced at the relevant hierarchy level.

Instances of the data/GeneralHelp model also contain a language code. If the user's language corresponds with the language code, then this instance is displayed. In the case where an instance is to be translated, a new instance can be created where:

- The instance language_code is updated to the new language, for example fr-fr.
- · Instance names should be unique.

If write access to the data/GeneralHelp model is available (contact VOSS), new help instances can be added and existing help instances can be modified. The process is summarized in the list below:

- The menu position of the instance (the value -1 will hide an instance). The list of instances can be sorted on the menu position column to show the order in which they will display on the General Help list on the Help browser tab.
- The display of an instance as a part of the model detail help of one or more selected models by adding Model Overwrite Details array instances to a data/GeneralHelp model instance. Options are available to:
 - Modify the title of the model help.
 - Modify the title of the General Help instance.
 - Show or hide the model help information (as obtained from the model or Field Display Policy).
 - Specify the position of the General Help instance relative to the model help information.

If more than one General Help instance is set to override the *same* selected model, *all* these overrides are applied where the positioning does not conflict. If positioning conflicts, the positioning of the *first* of the General Help instances (sorted alphabetically by instance name) is used.

If formatting is required in a new General Help model instance, the content can be written as ReStructured Text (http://en.wikipedia.org/wiki/ReStructuredText).

Note that:

- The Restructured Text is added as a *single string* in the JSON format file (line breaks in the text are to be replaced by the JSON escaped equivalent). This will be seen in the file when the <code>data/GeneralHelp</code> instance is exported.
- Model descriptions are also pop-up tooltips, so Restructured Text is not supported in attribute descriptions either in the model or Field Display Policy.
- There is no support for local image references, but remote references to images can be added in the Restructured Text by adding the URL to it.

4.5.2. Online Help Model Override Options

When adding or modifying an instance of the online help, the Model Override Options tab in the Admin Portal on the instance view provides settings to customize the context-sensitive help display.

Setting	Description	
Hide Model Help Title	Deprecated	
New Model Help Title	Deprecated	
Insert General Help Text Into Model Content	If Manipulate Model Dynamic Generated Help is enabled, this option also toggles the insert of the data/GeneralHelp instance text content.	
Hide General Help Section Title	If enabled, the data/GeneralHelp instance Menu Title or else Name is displayed.	
New General Help Section Title	By default, the RST title of the data/GeneralHelp instance is shown. This title can be replaced by entering text here.	
New Model General Help Paragraph Position	The position of the current data/GeneralHelp instance relative to the dynamically generated content is specified by an integer. If more than one instance of data/GeneralHelp will be applied to the same model type, the ordering of instances is set here.	
Manipulate Model Dynamic Generated Help	This setting is enabled to override the dynamically generated online help page with all the content and settings here.	
Model Dynamically Generated Help Paragraph Position	The position of the dynamically generated content relative current data/GeneralHelp instance to the is specified by an integer. If more than one instance of data/GeneralHelp will be applied to the same model type, the position of the dynamically generated instance is determined here.	
Hide API Help Link	The display of the default link to the API reference on the dynamically generated help page can be toggled.	
Hide Visualize Button	Deprecated	
Affected Model Type	Select the model to which the override applies. More than one override instance can be added so that the content of the data/GeneralHelp instance can override more than one model.	

4.6. Scripts

4.6.1. Scripts

It is possible to create and execute SSH scripts on devices from within the system. Scripts can be executed as part of a provisioning workflow.

Script files syntax is the Expect script syntax with the ability to add one of the following per line of the script:

- send data to a device and evaluate and substitute macros visible in the context hierarchy
- · define a regular expression for the response expected from the device
- branch to a next line based on a match to a response from a device
- · comments can be added to the script

Scripting has been tested with Cisco IOS devices.

Please note:

- Branching is only for one line in the script file and does not yet support blocks of commands.
- · Security: There is no control of what can be done or not done on the device.

In order to create and run a script, a supporting data model and IOS script device model Configuration Template can be used as a part of a Provisioning Workflow that is executed.

A GUI Rule called <code>ConfigurationTemplateOverride</code> for <code>device/ios/Script</code> is applied by default to the Configuration Template, which adds a <code>multiline</code> property to the <code>expect_script</code> field of the device model. This enables multiline input of the script.

The supporting model for the IOS device is data/Ios, to which an instance is added containing the host, port and authentication details of the device. This instance can then be selected as the Network Device Filter in the Provisioning Workflow if required. Alternatively, the Provisioning Workflow can define a context variable, say ios_details, that resolves to a particular data\Ios instance, for example { data.Ios.* | direction:local} }

In the IOS device model Configuration Template, the script itself is entered and can consist of a combination of Expect script syntax and system macros that are for example used for standard script blocks or variables for the selected data/IOS instance values.

When the Provisioning Workflow is executed, the transaction log can be inspected to examine the entire script with macros and variables referenced, as well as the device response.

4.6.2. Create and Run a Script

- 1. Add an instance to data/IOS. This instance contains the host, port and authentication details of the device.
- 2. Create a Configuration Template for the Target Model Type selected as device/ios/Script. A GUI Rule called ConfigurationTemplateOverride is applied by default to it to enable multiline input.

Macros in a script should however be written on one line.

In the device/ios/Script group on the Configuration Template, the following values can be entered:

- The Description value can be entered.
- The Expect Script value is the entered. The script can be entered over multiple lines. Variables
 can be used in the entered script sourced from either context variables or macros. Refer to the
 Expect Script Examples topic.
- 3. Create a Provisioning Workflow.
 - · Select the Workflow Operation as run.
 - Select the Step Type as model.
 - Select the Entity or Workflow as device/ios/Script
 - The Network Device Filter group's Device Instance can be a selected datalios instance, or if not, the device can be the value of a Provisioning Workflow Context variable that resolves to a particular datalios instance, for example {{data.los.* || direction:local}}.
 - The Configuration Template is the created template that contains the details of the script. If a Device Instance was added to the Provisioning Workflow, the script can reference it with the variable device_details, for example the data/Ios instance as {{device_details.host}} and {{device_details.host}}.

- · To run the script, execute the workflow.
- 4. Inspect the transaction. The details of the transaction show the script with all macros and variables resolved, as well as the response from the device.

4.6.3. Expect Script Examples

This section shows some examples of scripts entered into a Configuration Template for <code>device/ios/script</code> that can be used in a Provisioning Workflow to run the script. The examples show the usage of macros and variables.

Consider the following script snippet:

```
spawn telnet {{ pwf.ios_details.host }} 23\n
```

If the Provisioning Workflow from which the script is executed contains a context variable called ios_details with a value called {data.los.* || direction:local}}, then the device host will be the value of the data.los instance in the current hierarchy.

Consider the following script snippet:

```
send "ping {{data.Countries.ios-country_code | country_name: 'South Africa'}}\r"\n
```

The script will be:

```
send "ping ZA\r"\n
```

Consider the following multi-line macro called IOS_enable:

```
expect "HQ>\r"
send "enable\r"
expect "Password:\r"
send "{{device_details.enable_password}}\r"
```

The macro in a multiline script needs to be entered on a single line - without line breaks.

If we had macros for other snippets called <code>IOS_login</code> and <code>IOS_show_clock</code>, then the Configuration Template Expect Script value can be entered as these three macros:

```
{{IOS_login}}{{IOS_enable}}{{IOS_show_clock}}
```

4.6.4. Expect Script Import Format

This section shows examples of import files containing multiline scripts. The purpose of these examples are to show the format of the scripts in such files.

The JSON file format shows the line break characters (\n) in the multiline script. Note that the example here shows <code>expect_script</code> with three line breaks for display purposes.

```
{
  "meta": {},
  "resources": [
     {
        "meta": {
```

(continues on next page)

(continued from previous page)

```
"model_type": "data/ConfigurationTemplate",
       "pkid": "[pkid]",
       "schema_version": "0.1.8",
       "hierarchy": "sys",
       "tags": []
    },
    "data": {
      "target_model_type": "device/ios/Script",
      "name": "Multiline Test",
      "merge_strategy": "additive",
      "template": {
        "description": "Multiline Test",
        "expect_script": "ssh\nhost\npassword\n{{data.Countries.iso_country_code |
          country_name:'South Africa'}}\nping\nping {{data.Countries.iso_country_
-code |
          country_name:'South Africa'}}"
]
```

A MS Excel sheet cell that contains a multiline script would display in the spreadsheet editor across multiple lines (Using <Alt>-<Enter> for line breaks in MS Excel). The content of the cell would then display as:

```
ssh
host
password
{{data.Countries.iso_country_code | country_name:'South Africa'}}
ping
ping {{data.Countries.iso_country_code | country_name:'South Africa'}}
```

These formats can also be obtained by exporting an existing expect script in either JSON or Excel.

5. Move Customizations (Provider)

5.1. Network Device List Selection Rules Advanced Configuration

NDL popups are controlled by GUI Rules at hierarchy levels for model types. The device selection given GUI Rules, NDLs, NDLRs and Device Selection Rules are shown in this table.

GUI Rule	NDL(s)	NDLR	Use Popup	Use NDLR	Expected Result
N	N	N	•	•	Normal Device selection
N	Y	N	•	•	Normal Device selection
N	Y	Y	•	•	NDLR is used as target device
Y	Y	N	N	N	Normal Device selection and override with NDF in workflows
Y	Y	Y	Y	N	Pop up list of NDLs
Υ	Y	Y	Y	Y	Pop up list with NDLR as only option
Y	Y	N	Y	Y	Pop up an empty list with NDLR missing message
Y	N	N	N	N	Normal Device selection and override with NDF in workflows
Υ	Y	Y	N	N	NDLR is used as target device
Y	Y	Y	N	Y	NDLR is used as target device
Υ	Y	N	Y	N	Pop up list of NDLs (Most popular option)

The Rule Model Device Selection Type model also provides this functionality:

• The NDL device meta is available to the context in Provisioning Workflows. For example:

(continues on next page)

(continued from previous page)

```
},
    "bkey": "[\"NDL1\", \"P.C\"]",
    "data/UnityConnection": {
        "pkid": "54dc76be2afa4327de0d210b",
        "bkey": "[\"172.29.41.72\", \"443\", \"P.C\"]"
    }
}
```

• NDL device meta namespace device_meta is available in macros as: {{ device_meta.???}}, for example:

```
device_meta.ndl.name
device_meta.ndl.data/CallManager.pkid
```

- The [ndl] macro is available for use in GUI Rules similar to [hierarchy].
- An API parameter is available for the selected NDL when a GET request is sent for the Add form of a Relation. The value of [ndl] in the example below is a valid PKID for the NDL. For example:

```
GET /api/v0/relation/UswerCucmCucRel/add/?
hierarchy=[hierarchy]&
ndl=[ndl]&
schema=true&
schema_rules=true
```

This parameter is transformed in the subsequent Add calls to devices to a device parameter.

6. LDAP Sync

6.1. Change LDAP User Sync from Top-Down to Bottom-Up

Top-down user LDAP user management means that LDAP users are first added to VOSS-4-UC and then synced to Unified CM. The steps below provide details on how to change LDAP user sync from top-down to bottom-up, in other words, LDAP users on Unified CM are synced to VOSS-4-UC.


Important: The precautions below should be taken before carrying out the change.

6.1.1. Preliminaries


- · Take a VM snapshot before making any significant changes.
- Ensure that the LDAP server is in sync with VOSS-4-UC and that VOSS-4-UC is in sync with Unified CM.
- Make sure that you have the correct LDAP server information, or that someone is available who has
 the correct information.
- Make sure that Cisco and VOSS are aware of this change before commencing. L3 support staff need to be aware of the work being done beforehand.
- Always test the procedure for one user only first, using a Model Instance Filter. You need the assistance of VOSS-4-UC support
 - If the Model Instance Filter is to apply to the top down LDAP to VOSS-4-UC synced user, it should be on the device/ldap/user and the attribute cn - you can get the cn from the LDAP Synced users list.
 - If the Model Instance Filter is to apply to the bottom up, Unified CM to VOSS-4-UC synced user, it should be on the device/cucm/user and the attribute userid.

6.1.2. Checks


1. The Users list in VOSS-4-UC shows the user is "VOSS-LDAP Synced" and on the Provisioning Status tab for the user, the user is synced with both LDAP and CUCM.




2. The User Status column for the user in Unified CM is "Active LDAP synchronized User".



 The LDAP server is configured on CUCM and that the LDAP Attribute for User ID is the same as the Login Attribute Name on VOSS-4-UC. (On Unified CM: System > LDAP > Server and System > LDAP > LDAP Directory and search to find it or add it.)





- Confirm in the VOSS-4-UC schedules and transactions that recent LDAP VOSS-4-UC syncs have taken place and that Unified CM has the same user count as VOSS-4-UC.
- 5. Make sure in VOSS-4-UC that on **LDAP Management > LDAP User Sync** the user modes for Move, Delete and Purge are set to Manual. Note that when this configuration is saved, it will run a full LDAP sync.

6.1.3. Before you carry out the change


In VOSS-4-UC, make backups of LDAP server and configurations. The easiest way to do this is to export to JSON data from the following menu paths:

- LDAP Management > LDAP Sever
- LDAP Management > LDAP User Sync
- Administration Tools > Scheduling, LDAP Sync schedule
- LDAP Management > LDAP Authentication Users

This step is in case there are any issues. However, exporting is limited to 200 at a time, so for a customer with e.g. a 5K user count this is impractical. In that case a VM snapshot is recommended.

6.1.4. Make the change

- 1. In VOSS-4-UC, remove the instance under LDAP Management > LDAP User Sync for this customer.
- Check that the users in question show as local users on both VOSS-4-UC ("CUCM Local") and Unified CM ("Enabled Local User").





Enable the Cisco DirSync Service on Unified CM. Go to Cisco Unified Serviceability Tools > Service
 Activation. At the bottom of the page you will find Cisco DirSync Service. It will take some time to
 complete.



 Run an LDAP sync from Unified CM. Go to System > LDAP > LDAP Directory and select Perform Full Sync Now.



- 5. Check the user status of the user in Unified CM. The User Status will now show as "Active LDAP synchronized user"
- 6. In VOSS-4-UC, add the LDAP User Sync again and enable the LDAP Authentication Only option.




7. Run a DataSync from VOSS-4-UC with Unified CM. (I.e. the data sync with name that starts with "HcsPull")

6.1.5. To change LDAP User Data Sync back to Top Down


1. Stop the DirSync service on Unified CM.

Log into the CUCM Cisco Unified Serviceability page and go to **Tools > Control Center - Feature Services**. Select the Cisco DirSync service option and click **Stop**.



If this move is permanent, stop and deactivate the Cisco DirSync service on Unified CM.

- 2. In VOSS-4-UC, remove the Authenticate Only LDAP User sync.
- 3. In VOSS-4-UC, add an LDAP User Sync to do full LDAP syncs. (Or you can just import the JSON file exported earlier.)
- Go to User Management > Sync & Purge > LDAP Users and run the sync users from LDAP (Unselect the Remove Log Messages).



- 5. Check user in Unified CM and in VOSS-4-UC. The user status should be:
 - Unified CM: "LDAP Active Synced"
 - VOSS-4-UC: "VOSS-LDAP Synced"

7. Custom Configuration

7.1. Configuration Overview

Administrators with sufficient privileges have access to a number of resources that can be configured for various purposes.

Configuration can include:

- · clone and modification of Configuration Templates
- · the use of named macros in Configuration templates or resources
- Modification of the Site Defaults Doc
- · Modification of the Quick Add Group

By default, VOSS-4-UC provides a number of defaults in a collection of objects. Some of these defaults, such as the Default Site Dial Plan, are created when a Customer hierarchy is created. When a Site hierarchy is created, the defaults act as templates to provide site-specific values for the use of for example Subscriber creation at site level.

In particular, the following default templates result in site specific instances when a site is created:

- · Default Site Dial Plan
- · Default Site Defaults Doc
- · Default Quick Add Group

Administrators who have access to these resources can customize these templates so that all subsequent sites that are created, have modified site specific instances.

At a site level, the instances themselves can be modified so that subscribers that are added at the site, have these custom values applied to them. Site level modification can thus be made to:

- · Site level Site Defaults Doc
 - Contains site-specific values
 - Values are referenced by Configuration Templates at site level
 - Some values referenced by the Quick Add Group, for example Default CUC User Template
- · Site level Quick Add Group
 - Contains Configuration templates used when add Subscribers (Quick Add Subscriber)

Customization of resources may involve:

changing values (optionally using macros)

 changing or replacing Configuration Templates with newly cloned and created ones (optionally using macros)

7.2. Site Defaults Reference

When the End-to-End feature is installed and the system is provisioned for users, reference data representing a sample dial plan is stored as a template instance of a Site Defaults data model.

This reference data shows text values or combines default text and references with the feature's macros and configuration templates.

For example, when site hierarchy and user administration is carried out, input administrator data (stored as for example a named macro called SITENAME) is combined with this reference data to provide default or generated values. If a customer administrator at for customer "VS-Corp" created a site called "Boston", the line and call partitions associated with the site are called "Site-Boston" when the macro is resolved.

The sample dial plan is an instance of the site defaults and contains illustrative values. Where the name of the data refers to a Template, the Configuration Template itself contains or results in further data defaults that are applied when the End-to-End feature is used for user and site administration.

For example, the template called "Default CUCM RDP Template" sets a number of default Remote Destination Profile values when it is added:

Name	Value	
product	"Remote Destination Profile"	
protocol	"Remote Destination"	
description	"Created by default template"	
callInfoPrivacyStatus	"Default"	
protocolSide	"User"	
devicePoolName	"{{macro.CUCM_PHONE_devicePoolName}}"	
class	"Remote Destination Profile"	

The specified values for the CUCM Remote Destination Profile data are defaulted, while the macro called *macro.CUCM_PHONE_devicePoolName* looks up the Default Device Pool value for the Dial Plan name obtained from the Site Defaults instance. This value is based on the Customer ID and Site ID, for example "Cu12Si3-DevicePool" where the Customer ID is 12 and the Site ID is 3. This value is based on an ID lookup. These IDs are not reset during subsequent imports of the sample dial plan, so that existing instances on the system that use an ID will not be overwritten.

Most of these settings are populated with default values based on an example dial plan that ships with the core product. Typically, HCS templates overwrites these settings with different default values which are in line with a required dial plan.

All of the Day-2 features (provisioning of Subscriber, Phone, Line, and so on) have macros that point to the Site Defaults Document (SDD) when viewing the features in the GUI. This serves two main purposes:

- 1. It simplifies the administration of these features, because as soon as the administrator opens a GUI form to provision any of these features, the bulk of the settings are pre-populated with correct values (based on correct values in the SDD).
- 2. A abstracted view of Day-2 templates is possible by means of Field Display Policies that can hide complex and technical information while still populating these (hidden from view) by means of the SDD.

If changes are made in the SDD, for example new attributes are added, then pre-existing SDD instances must be manually updated to include these new attributes (if necessary).

7.3. Named Macros Overview

Named macros relate to two resources:

· Site Defaults Doc

These macros have a syntax is as in the following example:

```
data.SiteDefaultsDoc.defaultcuchtmlnotificationtemplate
```

Here the macro references an attribute of the specific Site Defaults Doc that is available at the hierarchy that the macro is called. In this case, the attribute name that is referenced, is defaultcuchtmlnotificationtemplate.

The Site Defaults Doc template that is used to resolve to values in site specific Site Defaults Doc instances is only configurable by an administrator with the *global* administrator role. Other provider, and customer level administrators can modify the individual instances at the specific site, while administrators at a site level can only inspect the values.

· Customizable Configuration Templates

Administrators - typically at provider or customer level have a list of Configuration Templates available from the **System Configuration** menu. These can be modified and cloned to a required hierarchy if customization is needed. In these Configuration Templates, macros may be referenced.

If the value to which a named macro resolves is required in a custom Configuration template, the named macro can then be added to the Configuration Template. Note however that Configuration Template customization involves more than the use of named macros.

The lists of named macros provides the macro name and its source code as reference. The macro name and the macro code which references to the Site Defaults Doc model attribute name describe its value in the Site Defaults Doc. No further explanation is needed in this case.

Where needed and the macro code is not self explanatory, a comment is added at the macro. Line breaks have been added to long macro source code strings.

The example below shows naming conventions, descriptions and line breaks.

macro.CUC HTML NotificationTemplateName

By default, the macro: DPSITE resolves to the site name at the current hierarchy, in other words: { { data.BaseSiteDAT.SiteName } }

The macro therefore resolves to the CUC notification template with the same name as the current site.

7.4. Quick Add Group Customization

Quick Add Groups provide a selection of service defaults for use in Subscriber management, in particular when the Quick Add Subscriber feature is used. More than one Quick Add Group can be available at a site so that it can be selected during the Quick Add Subscriber workflow. Refer to the topic on Quick Add Groups under the Site level documentation for an overview.

Administrators at customer hierarchy level and higher can modify Quick Add Groups. By default, a Quick Add Group is created for each site when it is created. The service defaults that are applied at the site level are stored in a Quick Add Group called "default" and serves as a template for the one created at the site. Administrators can view this template, but it cannot be modified.

The service defaults that are available in a Quick Add Group are stored as Configuration Templates to services.

Customization is carried out at the site level and can be done by either:

- creating new Quick Add Groups (and Configurations Templates)
- creating and selecting different Configuration Templates for use in an existing Quick Add Group.

7.5. Quick Add Subscriber Configuration

7.5.1. Quick Add Subscriber Provisioning Workflow Structure

The Quick Add Subscriber (QAS) feature uses a View model to define its schema that also ultimately defines:


- The form fields a user sees in the GUI
- The column headings in the QAS Bulk Loader sheet
- The attributes supported by the API endpoint (view/QuickSubscriber)

This View schema represents a simplified version of all possible Subscriber fields.

Associated with the View is a Provisioning Workflow (PWF) called AddQuickSubscriber that captures these simplified fields and combines or maps them into the various components (services) of a full Subscriber. The main purpose of this workflow is to execute an "Add relation/Subscriber" operation.

The "Add relation/Subscriber" operation in turn executes a second PWF called AddSubscriberNew, that separates out the data for each Subscriber component or service and executes an "Add" operation on the corresponding device models, for example on device/cucm/Phone.

It is inside this AddSubscriberNew workflow that the Config Templates of the selected Quick Add Group (QAG) is evaluated.



Since the Quick Add Group Config Templates (CFTs) are evaluated inside the AddSubscriberNew workflow, it is important that the Subscriber Relation field names *not* be those of the QAS View. Generally, all field values are made available to an executing PWF and is referred to as the *context*.

For example, refer to the diagram and notice the difference in field (attribute) naming between the QAS View and the Subscriber Relation schemas, for example username as opposed to userid. The difference is subtle, but very important: the Subscriber user name in the QAS workflow context (AddQuickSubscriber) is username, but in the Subscriber Relation workflow context (AddSubscriberNew) it is userid.

7.5.2. Subscriber Relation Context

When adding a Subscriber, multiple services are often added at the same time - for example, multiple Phones with multiple Lines.

During the "Add" operation, the AddSubscriberNew workflow therefore iterates (loops) over these added services and makes the data for each instance available in a *context variable*.

Consider for example the following workflow input context for adding a simple Subscriber:

(continues on next page)

(continued from previous page)

```
"routePartitionName": "Cul-DirNum-PT"
                              }
                         }
                     ]
                 }
            },
                 "name": "SEP000222333444",
                 "product": "Cisco Unified Client Services Framework",
                 "protocol": "SIP",
                 "lines": {
                     "line": [
                         {
                              "dirn": {
                                  "pattern": "82008",
                                  "routePartitionName": "Cu1-DirNum-PT"
                         }
                     ]
                 }
            }
        ]
    }
}
```

The input context shows there are two phones, each with one line. The AddSubscriberNew workflow will loop over the phones and put the entire contents of each instance in a context macro called {{ input. PhoneX }}.

Therefore, when it iterates over the first Phone, { { input.PhoneX } } will be equal to:

In particular, the input context variable {{ input.PhoneX.name }} will be equal to SEP111222333444. During the second iteration, {{ input.PhoneX.name }} will be equal to SEP000222333444.

7.5.3. Config Template Looping and Merging Overview

When the Quick Add Subscriber feature is used, the Subscriber Relation workflow (AddSubscriberNew) follows the same pattern for each device model being added. A base Config Template for the model is merged with the template specified in the Quick Add Group (QAG).

The purpose of the base template is to set fields which need to be hard coded to fulfill certain business rules, for example forcing the <code>ownerUserName</code> on Phone to the <code>userid</code> of the User.

This merging of Config Templates works seamlessly for the most part. However, the merge process becomes a little more complex when the Config Templates being merged contain lists which need to be looped through.

7.5.4. Config Template Looping


An example of a Config Template (CFT) loops is found in the Phone CFT because the Phone device model contains a list of Lines. In order to set template values for some of these line fields, one needs to iterate over the lines inside the CFT.

CFTs support this looping (foreach) mechanism, as can be seen on the GUI form when looking at a specific CFT instance.



The above screenshot illustrates how such a loop (Foreach) can be configured. The CFT is configured to loop over the macro {# input.PhoneX.lines.line #}. Remember, the PhoneX context variable contains a single instance of Phone data. So by referencing lines.line, we are referencing the *list of lines* associated to this specific Phone.

The Property indicates which field in the CFT we want to extend with each element of the lines.line list. Finally, the contents of each lines.line instance will be stored in {{ cft.LineX }} with each iteration. The cft namespace indicates the origin of the variable LineX.




The screenshot above illustrates how the iterated variable can be used in the lines.line field of the CFT.

The first macro in the Display Ascii input box will reference the firstName of the user in the Subscriber context, while the second macro references the pattern of the line instance being iterated over.

7.5.5. Config Template Merge Strategy

Given the example shown in the Config Template Looping topic, the use of CFTs in workflows is slightly more complicated, because the base CFT might already be implementing a CFT loop as seen in the example.

In this case, it is required for the QAG CFT to specify the correct Merge Strategy.



As can be seen from the image, since the base Phone CFT in the Subscriber Relation already implements a loop over lines, it is necessary for the QAG template to specify a "Replace" instead of "Additive" Merge Strategy.

This "replace" merge strategy allows the resulting lists of lines from the evaluated CFTs to be merged instead of being added together.

For reference, the following base CFTs implement a foreach loop:

- Phones (AddSubscriber PhoneLoop)
 - lines.line
 - lines.line.0.associatedEndusers.enduser
 - services.service
- Device Profile (AddSubscriber_DPLoop)
 - lines.line
 - lines.line.0.associatedEndusers.enduser
 - Services.service
- Remote Destination for Dual Mode Phone (AddSubscriber_RDLoopPhone)
 - lineAssociations.lineAssociation

86

- Remote Destination Profile SNR (AddSubscriber_RDPLoop)
 - lines.line
 - lines.line.0.associatedEndusers.enduser
- Remote Destination SNR (AddSubscriber_RDLoop)
 - lineAssociations.lineAssociation

7.6. Smart Add Phone Configuration

7.6.1. Custom Line Settings for Smart Add Phone Configuration Template

In order to customize the line settings of a custom Configuration Template to be used specifically with the Smart Add Phone feature, the cloned, customized template should be exported as a JSON file and edited manually.

Consider the data attribute snippet of an example Phone template JSON file before customization for custom lines:

```
"data": {
   "description": "Custom CUCM Phone Template",
   "name": "Custom Cisco 7945",
   "target_model_type": "device/cucm/Phone",
   "template": {
       "protocol": "SCCP",
       "softkeyTemplateName": "Standard Agent",
       "phoneTemplateName": "Standard 7945 SCCP",
       "callingSearchSpaceName": "(( input.Phone.callingSearchSpaceName == None )) \
         <{{macro.CUCM_PHONE_callingSearchSpaceName}}> \
         <{{input.Phone.callingSearchSpaceName}}>",
       "servicesUrl": "Both",
       "builtInBridgeStatus": "On",
       "useTrustedRelayPoint": "Default",
       "userlocale": "English United States",
        "enableExtensionMobility": "(( True ))",
       "commonDeviceConfigName": "Agent_CDC",
       "networkLocale": "United States",
       "packetCaptureMode": "None",
       "product": "Cisco 7945",
       "description": "Created by Custom Phone Template",
       "userLocale": "English United States",
       "deviceMobilityMode": "On",
       "certificateOperation": "No Pending Operation",
       "class": "Phone",
       "securityProfileName": "Cisco 7945 - Standard SCCP Non-Secure Profile",
       "protocolSide": "User",
       "commonPhoneConfigName": "Standard Common Phone Profile"
```

To customize this template for use with the Smart Add Phone feature and to add custom line settings, it requires additional elements in the data attribute group:

• A foreach loop method over lines with a line variable, e.g. LineX:

• Line specific customization for each line added on the Smart Add Phone input form on the Admin Portal represented by an attribute lines that contains a line list.

An example is shown below:

```
"lines": {
    "line": [
         {
             "maxNumCalls": "2",
             "displayAscii": "Test Site Phone",
             "busyTrigger": "1",
             "label": "{{ cft.LineX.directory_number }}",
             "e164Mask": "8005551212",
             "callInfoDisplay": {
                 "dialedNumber": "(( True ))",
                 "callerName": "(( True ))"
             },
             "asciiLabel": "{{ cft.LineX.directory_number }}",
             "display": "Test Site Phone"
         }
    ]
}
```

• Added attribute to template called merge_strategy and set to replace.

The example data attribute group below shows the additional customization integrated into the template. This template can then be selected from the **Phone Template** dropdown to customize the phone's line settings:

```
"data": {
   "name": "Custom Cisco 7945",
   "description": "Custom Smart Add Phone Template - Cisco 7945",
   "foreach": [
        {
            "property": "lines.line",
            "context_var": "LineX",
            "macro_list": "{# input.lines #}"
       }
   ],
   "merge_strategy": "replace",
   "target_model_type": "device/cucm/Phone",
   "template": {
       "protocol": "SCCP",
       "softkeyTemplateName": "Standard Agent",
       "phoneTemplateName": "Standard 7945 SCCP",
       "callingSearchSpaceName": "(( input.Phone.callingSearchSpaceName == None )) \
         <{{macro.CUCM_PHONE_callingSearchSpaceName}}> \
         <{{input.Phone.callingSearchSpaceName}}>",
       "servicesUrl": "Both",
       "builtInBridgeStatus": "On",
```

(continues on next page)

(continued from previous page)

```
"useTrustedRelayPoint": "Default",
"userlocale": "English United States",
"enableExtensionMobility": "(( True ))",
"commonDeviceConfigName": "Agent_CDC",
"networkLocale": "United States",
"packetCaptureMode": "None",
"product": "Cisco 7945",
"description": "Created by Custom Phone Template",
"userLocale": "English United States",
"deviceMobilityMode": "On",
"certificateOperation": "No Pending Operation",
"class": "Phone",
"securityProfileName": "Cisco 7945 - Standard SCCP Non-Secure Profile",
"protocolSide": "User",
"commonPhoneConfigName": "Standard Common Phone Profile",
"lines": {
    "line": [
        {
            "maxNumCalls": "2",
            "displayAscii": "Test Site Phone",
            "busyTrigger": "1",
            "label": "{{ cft.LineX.directory_number }}",
            "e164Mask": "8005551212",
            "callInfoDisplay": {
                "dialedNumber": "(( True ))",
                "callerName": "(( True ))"
            "asciiLabel": "{{ cft.LineX.directory_number }}",
            "display": "Test Site Phone"
        }
},
. . .
```

8. Configuration Reference

8.1. Reference Material

This section covers reference material for use in the customization of the Quick Add Subscriber feature in particular and custom configuration in general.

The material is divided into:

- Site Defaults Reference
- Quick Add Groups Configuration Template Reference
- · Named Macro Reference
- Quick Add Subscriber Workflow Macro Reference

8.2. Site Defaults Macros

8.2.1. Lines Site Defaults

Configuration Template applied to: line-cft

- · Default CUCM Line Partition
 - Macro: CUCM LINE routePartitionName
 - Default Value: Site-{{macro.SITENAME}}
- Default CUCM Line CSS
 - Macro: CUCM LINE shareLineAppearanceCssName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward No Answer CSS
 - Macro: CUCM_LINE_callForwardNoAnswer_callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward Busy Internal CSS
 - Macro: CUCM_LINE_callForwardBusyInt_callingSearchSpaceName
 - **Default Value**: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward No Answer Internal CSS

- Macro: CUCM_LINE_callForwardNoAnswerInt_callingSearchSpaceName
- Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward No Coverage CSS
 - Macro: CUCM_LINE_callForwardNoCoverage_callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward No Coverage Internal CSS
 - Macro: CUCM LINE callForwardNoCoverageInt callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward On Failure CSS
 - Macro: CUCM LINE callForwardOnFailure callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- · Default CUCM Line Call Forward On Failure Internal CSS
 - Macro: CUCM_LINE_callForwardNotRegisteredInt_callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward Not Registered CSS
 - Macro: CUCM_LINE_callForwardNotRegistered_callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward Busy CSS
 - Macro: CUCM_LINE_callForwardBusy_callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward Alternate Party CSS
 - Macro: CUCM LINE callForwardAlternateParty callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward Secondary CSS
 - Macro: CUCM LINE callForwardAll secondaryCallingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Line Call Forward All CSS
 - Macro: CUCM LINE callForwardAll callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}

8.2.2. Phones Site Defaults

Configuration Template applied to: SubscriberPhonePrePopulate

- Default CUCM Line Partition
 - Macro CUCM LINE routePartitionName
 - Default Value Site-{{macro.SITENAME}}
- · Default CUCM Phone Product
 - Macro: CUCM_PHONE_product
 - Default Value: Cisco 9971
- · Default CUCM Phone Security Profile
 - Macro: CUCM PHONE securityProfileName
 - Default Value: Cisco 9971 Standard SIP Non-Secure Profile
- Default CUCM Phone Protocol
 - Macro: CUCM PHONE protocol
 - Default Value: SIP
- Default CUCM Phone Common Profile
 - Macro: CUCM_PHONE_commonDeviceConfigName
 - Default Value: Standard Common Phone Profile
- · Default CUCM Location
 - Macro: CUCM PHONE locationName
 - Default Value: Cu{{data.BaseCustomerDAT.InternalCustomerID}}
 Si{{data.BaseSiteDAT.InternalSiteID}}-Location
- Default CUCM Phone Button Template
 - Macro: CUCM_PHONE_phoneTemplateName
 - Default Value: Standard 9971 SIP
- · Default CUCM Device Pool
 - Macro: CUCM PHONE devicePoolName
 - Default Value: Cu{{data.BaseCustomerDAT.InternalCustomerID}}
 Si{{data.BaseSiteDAT.InternalSiteID}}-DevicePool
- Default CUCM Phone Presence Group
 - Macro: CUCM PHONE presenceGroupName
 - Default Value: Standard Presence group
- Default CUCM Device CSS
 - Macro: CUCM_PHONE_callingSearchSpaceName
 - Default Value: EmergencyOnly-{{macro.SITENAME}}

8.2.3. Subscriber Site Defaults

Configuration Template applied to: <Not Applicable>

- Default CUCM Line Partition
 - Macro: CUCM LINE routePartitionName
 - Default Value: Site-{{macro.SITENAME}}
- · Default CUCM Phone Product
 - Macro: CUCM_PHONE_product
 - Default Value: Cisco 9971
- Default CUCM Phone Common Profile
 - Macro: CUCM PHONE commonDeviceConfigName
 - **Default Value**: Standard Common Phone Profile
- Default CUCM Location
 - Macro: CUCM PHONE locationName
 - Default Value: Cu{{data.BaseCustomerDAT.InternalCustomerID}}
 Si{{data.BaseSiteDAT.InternalSiteID}}-Location
- · Default CUCM Device Pool
 - Macro: CUCM_PHONE_devicePoolName
 - Default Value: Cu{{data.BaseCustomerDAT.InternalCustomerID}}
 Si{{data.BaseSiteDAT.InternalSiteID}}-DevicePool
- Default CUCM Device CSS
 - Macro: CUCM_PHONE_callingSearchSpaceName
 - Default Value: EmergencyOnly-{{macro.SITENAME}}
- Default CUCM Phone Line E164 Mask
 - Macro: CUCM_PHONE_lines_line_e164Mask
 - Default Value: 021575XXXX
- Default CUCM Phone Subscribe CSS
 - Macro: CUCM PHONE subscribeCallingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Device Profile Line E164 Mask
 - Macro: CUCM DP lines line e164Mask
 - Default Value: 021575XXXX
- Default CUCM Device Profile EMCC CSS
 - Macro: CUCM_DP_emccCallingSearchSpace
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Device Profile Product
 - Macro: CUCM_DP_product

- Default Value: Cisco 9971
- Default CUCM User Presence Group
 - Macro: CUCM_USER_presenceGroupName
 - **Default Value**: Standard Presence group
- Default CUCM User Subscribe CSS
 - Macro: CUCM USER subscribeCallingSearchSpaceName
 - **Default Value**: Intl24HrsEnh-{{macro.SITENAME}}
- · Default CUCM Remote Destination DND Option
 - Macro: CUCM RDP dndOption
 - Default Value: Call Reject
- · Default CUCM Remote Destination Profile CSS
 - Macro: CUCM RDP callingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUCM Remote Destination Profile Line E164 Mask
 - Macro: CUCM_RDP_lines_line_e164Mask
 - Default Value: 021575XXXX
- Default CUCM Remote Destination Profile ReRouting CSS
 - Macro: CUCM_RDP_rerouteCallingSearchSpaceName
 - Default Value: Intl24HrsEnh-{{macro.SITENAME}}
- Default CUC Subscriber Template
 - Macro: CUC USER templateAlias
 - Default Value: voicemailusertemplate

8.2.4. Quick Subscriber Site Defaults

Config Template applied to: <Not Applicable>

- · Default CUCM User Template
 - Macro: DEFAULT CUCM USER TEMPLATE
 - Default Value: Default CUCM User Template
- · Default CUCM Phone Template
 - Macro: DEFAULT_CUCM_PHONE_TEMPLATE
 - **Default Value**: Default CUCM Phone Template
- Default CUCM Line Template
 - Macro: DEFAULT_CUCM_LINE_TEMPLATE
 - Default Value: Default CUCM Line Template
- Default CUCM Device Profile Template

- Macro: DEFAULT_CUCM_DEVICEPROFILE_TEMPLATE
- Default Value: Default CUCM Extension Mobility Template
- Default CUCM RDP Template
 - Macro: DEFAULT_CUCM_RDP_TEMPLATE
 - Default Value: Default CUCM Remote Destination Profile Template
- Default CUCM RD Template
 - Macro: DEFAULT_CUCM_RD_TEMPLATE
 - Default Value: Default CUCM Remote Destination Template
- Default CUCM Jabber iPhone Template
 - Macro: DEFAULT CUCM JABBER IPHONE TEMPLATE
 - Default Value: Default CUCM Jabber iPhone Template
- Default CUCM Jabber Android Template
 - Macro: DEFAULT_CUCM_JABBER_ANDROID_TEMPLATE
 - **Default Value**: Default CUCM Jabber Android Template
- · Default CUC User Template
 - Macro: DEFAULT WEBEX USER TEMPLATE
 - Default Value: Default CUC User Template
- · Default Webex User Template
 - Macro: DEFAULT_CUC_USER_TEMPLATE
 - Default Value: Default Webex User Template

8.2.5. Voicemail Site Defaults

Configuration Template applied to: <Not Applicable>

- · Default CUC Phone System
 - Macro: CUC PHONE SYSTEM
 - Default Value: PhoneSystem
- Default CUC SMPP Provider
 - Macro: CUC_SMPP_PROVIDER
 - Default Value:
- Default CUC Subscriber Template
 - Macro: CUC HTML NotificationTemplateName
 - Default Value: Default Dynamic Icons
- · Default CUC HTML Notification Template
 - Macro: CUC_USER_templateAlias
 - **Default Value**: voicemailusertemplate

8.2.6. Webex Site Defaults

Configuration Template Applied: WebExUserPrePopulate

Menu	Macros	Default Value
<not applicable=""></not>	<not applicable=""></not>	<not applicable=""></not>

8.2.7. Hot Dial PLAR Site Defaults

Macros	Default Value	Derived From SDD Field	
<not applicable=""></not>	HotdialTZ	Africa/Johannesburg	

8.2.8. Hunt Groups Site Defaults

Configuration Template applied to: HuntGroupsPrePopulate

- Default CUCM Line Call Forward Busy CSS
 - Macro: Intl24HrsEnh-{{macro.SITENAME}}
 - Default Value: CUCM LINE callForwardBusy callingSearchSpaceNam
- Default CUCM Line Call Forward No Answer CSS
 - Macro: Intl24HrsEnh-{{macro.SITENAME}}
 - **Default Value**: CUCM_LINE_callForwardNoAnswer_callingSearchSpaceNam

8.2.9. Call Pickup Groups Site Defaults

Configuration Template applied to: CPGPrePopulate

- Default CUCM Call Pickup Partition
 - Macro: CUCM_CPUG_routePartitionName
 - Default Value: Site-{{macro.SITENAME}}

8.3. Quick Add Groups Configuration Template Reference

8.3.1. Default CUC User Template

applies to: device/cuc/User

Default CFT value:

• defaultcucsubscribertemplate: "voicemailusertemplate"

Value from a property of Site Defaults Doc for site, using a macro (line break added):

```
{{ data.SiteDefaultsDoc.defaultcucsubscribertemplate | | direction:local }}
```

8.3.2. Default CUCM Phone Template

applies to: device/cucm/Phone

Internal workflow settings (not customizable):

- CFT has variables to loop over the lines on a Phone
- · CFT replaces any existing values as opposed to only adding values

Default CFT values:

- builtInBridgeStatus: "Default"
- callingSearchSpaceName:

```
"(( input.Phone.callingSearchSpaceName == None ))
  <{{macro.CUCM_PHONE_callingSearchSpaceName}}>
  <{{input.Phone.callingSearchSpaceName}}>"
```

The CFT uses an IF-THEN-ELSE type macro to resolve the value. The macro first checks if a value for <code>callingSearchSpaceName</code> is available in the input context of the workflow (user input or for example by other means in the workflow such as another CFT). Otherwise, a named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of <code>defaultdevicecss</code>.

- certificateOperation: "No Pending Operation"
- class: "Phone"
- commonPhoneConfigName: "Standard Common Phone Profile"
- description: "Created by default template"
- deviceMobilityMode: "On"
- devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

```
• lines.line[0].display: "{{ input.firstName }}"
```

Each line associated to a phone will have the user first name that is available as input context to the workflow. The macro notation input is the namespace for the context reference that is available during the workflow. The value firstName is a property of the Subscriber object that is created and is available for the input form of the Quick Add Subscriber feature.

• locationName:

```
{{ macro.CUCM_PHONE_locationName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultLOC.

• packetCaptureMode: "None"

• phoneTemplateName: "Standard 9971 SIP"

• product: "Cisco 9971"

• protocol: "SIP"

• protocolSide: "User"

• securityProfileName: "Cisco 9971 - Standard SIP Non-Secure Profile"

• useTrustedRelayPoint: "Default"

8.3.3. Default CUCM RDP Template

applies to: device/cucm/RemoteDestinationProfile

Default CFT values:

• callInfoPrivacyStatus: "Default"

class: "Remote Destination Profile"

• description: "Created by default template"

• devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

• product: "Remote Destination Profile"

• protocol: "Remote Destination"

• protocolSide: "User"

8.3.4. Default CUCM RD Template

applies to: device/cucm/RemoteDestination

Default CFT values:

• answerTooLateTimer: "19000"

• answerTooSoonTimer: "1500"

• delayBeforeRingingCell: "4000"

8.3.5. Default CUCM User Template

applies to: device/cucm/User

Default CFT values:

• enableMobility: "((True))"

The value ((True)) is a macro in the system.

presenceGroupName: "Standard Presence group"

8.3.6. Default Webex User Template

By default, the template has no customization.

8.3.7. Default CUCM Device Profile Template

applies to: device/cucm/DeviceProfile

Default CFT values:

• description: "Created by default template"

• phoneTemplateName: "Standard 9971 SIP"

• product: "Cisco 9971"

• protocol: "SIP"

8.3.8. Default CUCM Jabber Android Template

applies to: device/cucm/Phone

Default CFT values:

- builtInBridgeStatus: "Default"
- callingSearchSpaceName:

```
"(( input.Phone.callingSearchSpaceName == None ))
  <{{macro.CUCM_PHONE_callingSearchSpaceName}}>
  <{{input.Phone.callingSearchSpaceName}}>"
```

The CFT uses an IF-THEN-ELSE type macro to resolve the value. The macro first checks if a value for <code>callingSearchSpaceName</code> is available in the input context of the workflow (user input or for example by other means in the workflow such as another CFT). Otherwise, a named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of <code>defaultdevicecss</code>.

- certificateOperation: "No Pending Operation"
- class: "Phone"
- commonPhoneConfigName: "Standard Common Phone Profile"
- description: "Created by default template"
- deviceMobilityMode: "Default"
- devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

• locationName:

```
{{ macro.CUCM_PHONE_locationName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultLOC.

- packetCaptureMode: "None"
- phoneTemplateName: "Standard Dual Mode for Android"
- product: "Cisco Dual Mode for Android"
- protocol: "SIP"
- protocolSide: "User"
- securityProfileName: "Cisco Dual Mode for Android Standard SIP Non-Secure Profile"
- sipProfileName: "Standard SIP Profile"
- useTrustedRelayPoint: "Default"

8.3.9. Default CUCM Jabber CSF Template

applies to: device/cucm/Phone

Default CFT values:

- builtInBridgeStatus: "Default"
- callingSearchSpaceName:

```
"(( input.Phone.callingSearchSpaceName == None ))
  <{{macro.CUCM_PHONE_callingSearchSpaceName}}>
  <{{input.Phone.callingSearchSpaceName}}>"
```

The CFT uses an IF-THEN-ELSE type macro to resolve the value. The macro first checks if a value for <code>callingSearchSpaceName</code> is available in the input context of the workflow (user input or for example by other means in the workflow such as another CFT). Otherwise, a named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of <code>defaultdevicess</code>.

- certificateOperation: "No Pending Operation"
- class: "Phone",
- commonPhoneConfigName: "Standard Common Phone Profile",
- description: "Created by default template",
- deviceMobilityMode: "Default",
- devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

• locationName:

```
{{ macro.CUCM_PHONE_locationName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultLOC.

- packetCaptureMode: "None"
- phoneTemplateName: "Standard Client Services Framework"
- product: "Cisco Unified Client Services Framework"
- protocol: "SIP"
- protocolSide: "User"
- securityProfileName: "Cisco Unified Client Services Framework Standard SIP Non-Secure Profile"
- sipProfileName: "Standard SIP Profile"
- useTrustedRelayPoint: "Default"

8.3.10. Default CUCM Jabber iPad Template

applies to: device/cucm/Phone

Default CFT values:

- builtInBridgeStatus: "Default"
- callingSearchSpaceName:

The CFT uses an IF-THEN-ELSE type macro to resolve the value. The macro first checks if a value for <code>callingSearchSpaceName</code> is available in the input context of the workflow (user input or for example by other means in the workflow such as another CFT). Otherwise, a named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of <code>defaultdevicecss</code>.

- certificateOperation: "No Pending Operation"
- class: "Phone"
- commonPhoneConfigName: "Standard Common Phone Profile"
- description: "Created by default template"
- deviceMobilityMode: "On"
- devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

• locationName:

```
{{ macro.CUCM_PHONE_locationName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultLOC.

- packetCaptureMode: "None"
- phoneTemplateName: "Standard Jabber for Tablet"
- product: "Cisco Jabber for Tablet"
- protocol: "SIP"
- protocolSide: "User"
- securityProfileName: "Cisco Jabber for Tablet Standard SIP Non-Secure Profile"
- useTrustedRelayPoint: "Default"

8.3.11. Default CUCM Line Template

applies to: device/cucm/Line

Default CFT values:

• callingSearchSpaceName:

```
{{ macro.CUCM_LINE_shareLineAppearanceCssName }}
```

• routePartitionName:

```
{{ macro.CUCM_LINE_routePartitionName }}
```

• shareLineAppearanceCssName:

```
{{ macro.CUCM_LINE_shareLineAppearanceCssName }}
```

8.3.12. Default CUCM Jabber iPhone Template

applies to: device/cucm/Phone

Default CFT values:

- builtInBridgeStatus: "Default"
- callingSearchSpaceName:

```
"(( input.Phone.callingSearchSpaceName == None ))
  <{{macro.CUCM_PHONE_callingSearchSpaceName}}>
  <{{input.Phone.callingSearchSpaceName}}>"
```

The CFT uses an IF-THEN-ELSE type macro to resolve the value. The macro first checks if a value for <code>callingSearchSpaceName</code> is available in the input context of the workflow (user input or for example by other means in the workflow such as another CFT). Otherwise, a named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of <code>defaultdevicecss</code>.

• certificateOperation: "No Pending Operation"

- class: "Phone"
- commonPhoneConfigName: "Standard Common Phone Profile"
- description: "Created by default template"
- deviceMobilityMode: "Default"
- devicePoolName:

```
{{ macro.CUCM_PHONE_devicePoolName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultDP.

• locationName:

```
{{ macro.CUCM_PHONE_locationName }}
```

A named macro is used to resolve the value. The named macro references the value from the Site Defaults Doc at the current hierarchy, in particular, from the value of defaultLOC.

- packetCaptureMode: "None"
- phoneTemplateName: "Standard Dual Mode for iPhone"
- product: "Cisco Dual Mode for iPhone"
- protocol: "SIP"
- protocolSide: "User"
- securityProfileName: "Cisco Dual Mode for iPhone Standard SIP Non-Secure Profile"
- useTrustedRelayPoint: "Default"

8.4. Named Macro Reference

8.4.1. Named Macros Available to Administrators

The macros that are available to administrators can be seen at two sources:

- · on the tabs of the Site Defaults doc
- in Configuration Templates that are available to administrators for inspection, cloning and customization

The lists group macros in the same categories as they are in the tabs on the user interface for the Site Defaults doc, while the macros that are only in Configuration Templates are listed together.

8.4.2. Named Macros - Site Defaults General

```
    macro.CUCM_UDT_devicePool
        {{ data.SiteDefaultsDoc.defaultDP }}
    macro.CUCM_PHONE_locationName
        {{ data.SiteDefaultsDoc.defaultLOC }}
```

macro.SITE USP PROFILE

The additional specified ensures that a User Profile value is only searched for in a Site Defaults Doc at the current hierarchy, so that the hierarchy at which the Site Defaults Doc is available is limited more strictly.

macro.CUCM_HPILOT_routePartitionName

```
{{ data.SiteDefaultsDoc.defaulthppt }}
```

macro.CUCM CPUG routePartitionName

```
{{ data.SiteDefaultsDoc.defaultcpupt }}
```

macro.CUCM CPARK routePartitionName

```
{{ data.SiteDefaultsDoc.defaultcppt }}
```

macro.CUCM MEETME routePartitionName

```
{{ data.SiteDefaultsDoc.defaultmmpt }}
```

macro.DEFAULT_CUCM_GROUP

```
{{ data.SiteDefaultsDoc.defaultcucmgroup }}
```

macro.CUCM_RDP_callingSearchSpaceName

```
{{ data.SiteDefaultsDoc.default_rdp_css }}
```

macro.CUCM RDP devicePoolName

```
{{ data.SiteDefaultsDoc.defaultDP }}
```

macro.CUCM_RDP_dndOption

```
{{ data.SiteDefaultsDoc.default_cucm_rdp_dndoption }}
```

8.4.3. Named Macros - Site Defaults Device

macro.CUCM PHONE product

```
{{ data.SiteDefaultsDoc.default_cucm_phone_product }}
```

macro.CUCM PHONE protocol

```
{{ data.SiteDefaultsDoc.default_cucm_phone_protocol }}
```

macro.CUCM PHONE securityProfileName

```
{{ data.SiteDefaultsDoc.default_cucm_phone_securityprofile }}
```

```
    macro.CUCM PHONE softkeyTemplateName

 {{ data.SiteDefaultsDoc.default_cucm_phone_softkey }}

    macro.CUCM_PHONE_sipProfile

 {{ data.SiteDefaultsDoc.default_cucm_phone_sipprofile }}

    macro.CUCM PHONE presenceGroupName

 {{ data.SiteDefaultsDoc.default cucm phone presencegroup }}

    macro.CUCM PHONE commonDeviceConfigName

 {{ data.SiteDefaultsDoc.default_cucm_phone_commondeviceconfiq }}

    macro.CUCM PHONE lines line e164Mask

 {{ data.SiteDefaultsDoc.default_cucm_phone_e164_mask }}

    macro.CUCM PHONE callingSearchSpaceName

 {{ data.SiteDefaultsDoc.defaultdevicecss }}

    macro.CUCM_DP_product

 {{ data.SiteDefaultsDoc.default_cucm_dp_product }}

    macro.CUCM_DP_protocol

 {{ data.SiteDefaultsDoc.default cucm dp protocol }}

    macro.CUCM DP phoneTemplateName

 {{ data.SiteDefaultsDoc.default_cucm_dp_template }}

    macro.CUCM_DP_lines_line_e164Mask

 {{ data.SiteDefaultsDoc.default_cucm_dp_e164_mask }}

    macro.CUCM DP emccCallingSearchSpace

 {{ data.SiteDefaultsDoc.default_dp_emcc_css }}

    macro.CUCM_RDP_rerouteCallingSearchSpaceName

 {{ data.SiteDefaultsDoc.default rdp rr css }}

    macro.CUCM RDP lines line e164Mask

 {{ data.SiteDefaultsDoc.default_cucm_rdp_e164_mask }}

    macro.CUCM_PHONE_devicePoolName

 {{ data.SiteDefaultsDoc.defaultDP }}

    macro.CUCM PHONE enableExtensionMobility

 {{ data.SiteDefaultsDoc.default_cucm_phone_enableEM }}
```

8.4.4. Named Macros - Site Defaults Line

Note: These macros will also reference a workflow variable move_to_hn_pkid if it is set. The variable is used in the default "Move Subscriber" workflows. If the variable value is available, it is used as the target hierarchy for macro execution.

If the macros are used in workflows outside of the default "Move Subscriber" workflows, set the variable - for example when using the macros in Line Configuration Templates.

CUCM_LINE_presenceGroupName

macro.CUCM_LINE_shareLineAppearanceCssName

CUCM_LINE_vmprofile

macro.CUCM_LINE_routePartitionName

CUCM_LINE_callForwardAll_callingSearchSpaceName

CUCM LINE callForwardAll secondaryCallingSearchSpaceName

CUCM_LINE_callForwardAlternateParty_callingSearchSpaceName

CUCM LINE callForwardBusyInt callingSearchSpaceName

CUCM_LINE_callForwardBusy_callingSearchSpaceName-2

• CUCM LINE callForwardNoAnswerInt callingSearchSpaceName

CUCM LINE callForwardNoAnswer callingSearchSpaceName

CUCM LINE callForwardNoCoverageInt callingSearchSpaceName

CUCM LINE callForwardNoCoverage callingSearchSpaceName

CUCM LINE callForwardNotRegisteredInt callingSearchSpaceName

CUCM LINE callForwardNotRegistered callingSearchSpaceName

CUCM LINE callForwardOnFailure callingSearchSpaceName

8.4.5. Named Macros - Site Defaults User

macro.DEFAULT_USER_ROLE

```
(( data.SiteDefaultsDoc.defaultuserrole == None ))
  <selfservice> <{{ data.SiteDefaultsDoc.defaultuserrole}}>
```

If a default user role is not specified in the Site Defauls Doc, then the role value is the selfservice role.

macro.CUCM_USER_presenceGroupName

```
{{ data.SiteDefaultsDoc.default_cucm_user_presencegroup }}
```

macro.CUCM_USER_serviceProfile

```
{{ data.SiteDefaultsDoc.default_cucm_user_serviceprofile }}
```

macro.CUCM USER subscribeCallingSearchSpaceName

```
{{ data.SiteDefaultsDoc.defaultlinecss }}
```

8.4.6. Named Macros - Site Defaults CUC

macro.CUC PHONE SYSTEM

```
{{ data.SiteDefaultsDoc.defaultcucphonesystem }}
```

macro.CUC_USER_templateAlias

```
{{ data.SiteDefaultsDoc.defaultcucsubscribertemplate }}
```

macro.CUC_SMPP_PROVIDER

```
{{ data.SiteDefaultsDoc.defaultcucsmppprovider }}
```

8.4.7. Named Macros - Site Defaults Hotdial

macro.CUCM_DP_defaultplarcss

```
{{ data.SiteDefaultsDoc.defaultplarcss }}
```

macro.CUCM_HOTDIAL_defaultplarcss

```
{{ data.SiteDefaultsDoc.defaultplarcss }}
```

8.4.8. Named Macros in Configuration Templates

macro.CUC_HTML_NotificationTemplateName

By default, the macro: DPSITE resolves to the site name at the current hierarchy, in other words: {{ data.BaseSiteDAT.SiteName }}

The macro therefore resolves to the CUC notification template with the same name as the current site.

macro.CUC_DEFAULT_USER_TEMPLATE

Standard Common Phone Profile

macro.CUCM_LINE_callForwardBusy_callingSearchSpaceName

```
{{ fn.evaluate macro.CUCM_LINE_callForwardBusy_callingSearchSpaceName-2 }}
```

The macro uses a macro function call to resolve another macro. Refer to the notes at the relevant macro.

macro.NEXT_AVAILABLE_LINE

```
{{ data.InternalNumberInventory.internal_number |
   used:fn.false,available:fn.true |
   direction:up,limit:1 }}
```

Returns the next available line from the internal number inventory.

macro.MappedE164fromDNLookup

```
{{ fn.get_e164_number cft.LineX.dirn.pattern }}
```

Look up the mapped E164 number given a DN.

macro.E164MaskMappedorPubNum

macro.CUCM UDT commonPhoneProfile

Standard Common Phone Profile

macro.CUCM_UDT_ownerUserId

Current Device Owner's User ID

macro.CUCM_UDT_phoneButtonTemplate

Universal Device Template Button Layout

macro.SITENAME

```
{{ data.VOSS-Site-DialPlan.SiteName }}
```

During site creation, an instance of data/VOSS-Site-DialPlan is created at the site hierarchy. This data model stores a reference to the name of the site.

8.4.9. Pull Sync Delete Threshold

During a data sync where you delete a VOSS-4-UC resource from the device so that the key is in the VOSS-4-UC list but not in the 'device' list, a pull sync will remove the resource in VOSS-4-UC.

In order to manage the number of resources that are deleted on VOSS-4-UC during this process, a named macro with:

- name: PULL_SYNC_DELETE_THRESHOLD_<device_type>
- macro: number
- hierarchy: the hierarchy where the sync takes place.

Upon a data sync of the device type, local deletes will be restricted to the number defined in the macro.

Note: The macro value is a JSON string containing the number, e.g. "macro": "2". If the macro is created on the GUI, simply type in the number as value.

In JSON format, the named macro is for example as in the snippet below:

```
[...]
"meta": {
    "model_type": "data/Macro",
    "hierarchy": "sys.hcs.CS-P.CS-NB.AAAGlobal",
    "tags": []
},

"data": {
    "macro": "2",
    "name": "PULL_SYNC_DELETE_THRESHOLD_skypeforbusinessonline",
    "description": "PULL_SYNC_DELETE_THRESHOLD_skypeforbusinessonline"
}
[...]
```

Note: The model name following the data/ model type is inserted into the macro name.

The table below maps the device type names as seen on the Data Sync GUI to the related model in full (remove data/ in the macro):

Device Type	Full data model name
"Active Directory"	data/Activedirectory
"Active Directory Hybrid"	data/Activedirectoryhybrid
"Cisco HCM-F"	data/Hcmf
"Cisco Unified CM"	data/CallManager
"Cisco Unified Contact Center Express"	data/Cuccx
"Cisco Unity Connection"	data/UnityConnection
"Cisco WebEx"	data/WebEx
"Exchange"	data/exchange
"Exchange Hybrid"	data/exchangehybrid
"Exchange Online"	data/exchangeonline
"LDAP"	data/Ldap
"Microsoft Online"	data/msonline
"PowerShell"	data/powershell
"Service Now"	data/ServiceNow
"SkypeForBusiness"	data/skypeforbusiness
"SkypeForBusiness Hybrid"	data/skypeforbusinesshybrid
"SkypeForBusiness Online"	data/skypeforbusinessonline
"Spark"	data/Spark

If during a sync the macro is available and the number value in the macro is reached while there are more instances, the sync log will also show an error. If no macro is defined as above, then the pull sync will remove all local instances on VOSS-4-UC.

9. Macro Reference

9.1. Macros

Macros are used to return data from the system in various formats, to test for conditions, map data from Admin Portal or bulk loader input to various elements in the system (in conjunction with configuration Itemplates) and to access data in workflow steps.

Various macro functions are available. These serve as boolean operators or can be used to carry out various numeric functions, string manipulation functions, list functions, time functions, and hierarchy related functions.

Macros can be created for re-use, named and stored as an instance of the Macro data model. When re-used, the reference prefix syntax is of the format: *macro.<macroname>*.

Named macros and macro functions can be nested within other macros.

Refer to the Macro Reference topics.

9.2. Macro Syntax

9.2.1. Macro Syntax Brackets

Macros can have any of the following markup:

• {{ and }}

indicate macros that resolve to single values. The value can also return an object. A direction parameter is also available for hierarchy searching. This is indicated by $|\cdot|$. Refer to the topic on SELECT-FROM-WHERE type macros for details.

Any number of single opening and closing brackets ({ and }) can also occur inside these scalar macros.

• { # and # }

indicate macros that resolve to lists of values.

• {% and %}

indicate macros that resolve to dictionaries

• ((and))

indicate macros that test for a condition are enclosed in round brackets ((and)) - these macros evaluate to True or False

The comparison operators that are available for these macros are: ==, !=, <, >, <=, >=.

The OR operator in a test is |, for example:

```
(( device.cuc.PagerDevice.Undeletable| ObjectId:input.ObjectId|
    direction:local == False ))
```

• ((test)) <if value> <else value>

IF ELSE type conditional macro.

• ((test)) <value> ((test)) <value> <value>

IF ELSEIF ELSE-type macros combine tests and result values if the test resolves to True or False. The logic is IF (test) THEN <value> ELSE IF (test) THEN <value>.

Example:

```
((self.a == self.b)) <foo-{{CallManager.host}}>
  ((self.b == self.c)) <foo-{{CallManager.username}}>
  <foo-{{CallManager.version}}>
```

This macro tests for the equality of values in a calling model (referenced by 'self') and returns an evaluation for the condition that is True. The evaluation refers in dot notation to attributes of a Data Model called 'CallManager' and concatenates the result with a string 'foo-'.

 'SELECT FROM WHERE'-type macros returning single-, dictionary- and list type values and can take parameters.

The format is:

- {{ SELECT FROM | WHERE }}
- {% SELECT FROM | WHERE %}
- {# SELECT FROM | WHERE #}

These types and their parameters are illustrated in the topic on 'SELECT FROM WHERE' Macros.

9.2.2. Macro Syntax Multiline

Macros can contain line breaks. The Admin Portal provides a multiline input box for macros. For example:

If a macro that returns a string has string prefix or suffix, for example, a macro with the value:

```
"AAA {{data.Countries.iso_country_code | country_name:'South Africa'}}
AAA"
```

will output:

```
AAA
ZAF
AAA
```

A JSON export of the macro will show the line breaks, for example:

```
"data": {
   "macro": "AAA\n{{data.Countries.iso_country_code | country_name:'South Africa'}}\nAAA
   \_",
   "name": "MACRO1"
}
```

If the macro is an Expect script:

```
expect "HQ>\r"
send "enable\r"
expect "Password:\r"
send "{{device_details.enable_password}}\r"
```

Line breaks cannot be entered inside a macro, for example:

```
"AAA {{data.Countries.iso_country_code | country_name:'South Africa'}}
AAA"
```

is not valid.

9.2.3. Dot notation

A dot-notation is used to refer to a macro function, model attribute, a defined variable, step reference, or non-attribute value in the model schema.

- fn.macrofunction_name identifies a macro function. Refer to the Macro Functions topics in the Advanced Configuration Guide.
- self.attribute is used to refer to the current value of an attribute in the model where the macro applies.
 - Here, *attribute* should be an attribute name of the calling model in which the macro is referenced (usually a configuration template). In other words, the macro should be associated with a configuration template of a resource that is referenced.
- previous.attribute is used to the previously saved value of an attribute as opposed to the existing value in the case where a model is updated.
- *input.attribute* identifies the values input via any of: the GUI, bulk load, provisioning workflow foreach variable or context.
- pwf.variablename identifies a variable value defined as a provisioning workflow set step variable.
- cft.attribute identifies the values input in a configuration template via the current value of the context_var of a foreach loop of a configuration template.
- modelname.attribute this notation defaults to the Data Model type.
- modeltype.modelname.attribute is used for other non-data model types.
- modeltype.modelname.attribute.NUMBER is used to refer to attribute NUMBER-1 where there is more than one attribute, that is, the first attribute reference is modeltype.modelname.attribute.0.
 See the Macro examples section. The NUMBER can also be a wild card, as in {# device.cucm.Phone.lines.line.*.dirn #}
- macro.name is used to refer to a defined macro by name.
- workflow.stepSTEPNUMBER.pkid a hierarchy value to override the **Context Hierarchy** by specifying the context using the pkid of stepSTEPNUMBER, where STEPNUMBER can be 1, 2 and so on.

Non-attribute notation allows the following for a model:

```
__pkid__bkey__hierarchy__hierarchy_friendly_path__hierarchy_friendly_parent_path
```

Some examples of this syntax:

```
{# data.Countries.__pkid #}
{# data.CallManager.__bkey #}
{{ data.CallManager.__bkey | host:172.29.248.150 }}
{{ data.CallManager.__hierarchy | host:172.29.248.150 }}
{{ data.CallManager.__hierarchy_friendly_path | host:172.29.248.150 }}
{{ data.CallManager.__hierarchy_friendly_parent_path | host:172.29.248.150 }}
```

The hierarchy fields can be combined with model attribute names in a comma separated, for example:

Output snippet:

- To indicate sequence instance with *SEQ* the value is a loop sequence number starting from 1 or a wizard step number:
 - It is obtained from a Foreach List Macro in a provisioning workflow or a Foreach Elements loop in a configuration template.

This value can be used to refer to an *attribute* of a model. An array item in a configuration template has a **Foreach Elements** loop with a variable phoneX:

```
{ # self.Phone.{{fn.subtract input.phoneX.SEQ,1}}.lines.line #}
```

that refers to an attribute (line in a list of phones), starting with the first one:

```
self.Phone.O.lines.line
```

This value can be used to refer to a Wizard step (stepSTEPNUMBER) in its configuration template.
 A Foreach Elements loop with a variable step that holds a list of STEPNUMBER obtained from the wizard:

```
{# input.define_wizard_steps #}
```

so that stepSTEPNUMBER can be incremented with:

```
step{{cft.step.SEQ}}}
```

9.2.4. SELECT FROM WHERE Macro Syntax

The types of return values are indicated by the syntax:

- {{SELECT FROM | WHERE}} for single values or objects
- {%SELECT FROM | WHERE%} for dictionaries
- {#SELECT FROM | WHERE#} for lists

The SELECT FROM part is a model reference and uses dot notation.

For lists and dictionaries, the SELECT FROM notation can contain a wild card asterisk * to return all matching values.

Examples returning all User attributes:

```
{# data.User.* |username: js54321, last_name: 'van Dever' #}
{% data.User.* |username: js54321 %}
```

The WHERE part is one or more comma-separated name:value pairs of attribute values of the model reference. If the value itself has a comma, it should be wrapped in quotes.

For example:

```
{{ data.Address.* | street_name: 'The Willows, Park Crescent' }}
```

The value can also contain:

• a reference to an empty field, as in:

```
{# data.User.* / email: null #}
```

• a reference to a defined macro used to return a value, as in:

```
{ # data.DRTPBXMeta.* | PBX:macro.getHost #}
```

• a boolean value using the corresponding macro function, as in:

```
{{ data.DATA1.name | code: fn.true }}
```

The WHERE part also supports:

· Asterisk * for filtering.

Examples:

```
{{ device.cucm.Phone.lines.line | name: "SEPD13B004F0719",
    lines.line.*.dirn.pattern:"1006",
    lines.line.*.dirn.routePartitionName:
    "AllowEmerCalls-NewSite4" }}
```

If there is a * in the WHERE clause:

- the results list is reduced with that specific clause
- the specific WHERE clause is a list

Note that only one * is supported and if the WHERE clause has an invalid field name, it will be ignored and still return the data.

• regular expression type syntax:

```
field:/regex/
```

Note: regular expression syntax should not be used when querying collections with more than 500 members.

Examples:

```
{ # data.Countries.country_name | country_name:/ia$/ #}
```

returns names that end in "ia":

```
[ "Australia", "Saudi Arabia" ]
```

To exclude a list of countries matching "ia" in the name:

```
{# data.Countries.country_name | country_name:/[^ia]$/ #}
```

To carry out a case-insensitive search, add the regex parameter:

```
{# data.UserSavedSearch | username: /input.username/i #}
```

Will for example match:

```
CS-PADMIN@csp.com
CS-PAdmin@csp.com
cs-padmin@csp.com
```

Macros cannot be nested in the regex. This will *not* work:

```
{# data.Countries.* | iso_country_code: /[^({{input.ISO}})]/ #}
```

But this will work:

Macro ISO_REGEX:

```
/[^({{input.ISO}})]/
```

Macro:

```
{ # data.Countries.* | iso_country_code:macro.ISO_REGEX #}
```

· attributes not in the data of the model schema

```
- __pkid
```

- _ __device_pkid
- **-** ___bkey
- __hierarchy
- __hierarchy_friendly_path
- __hierarchy_friendly_parent_path

Examples:

- Given the following macro USA_pkid:

```
{{ data.Countries.__pkid | iso_country_code:USA }}
```

then macro:

```
{{ data.Countries.country_name | __pkid:macro.USA_pkid }}
```

will return:

```
{"United States of America"}
```

- Using ___device_pkid:

```
{{ device.cucm.CallManager.__device_pkid | name:CM_sol-cucm-ob-01}}
```

returns:

```
5c6f4ad0de894e0014e5b84c
```

Note that when using __hierarchy_friendly_path in a WHERE clause, the option clause *direction* will be ignored, for example:

```
{# data.Countries.* | __hierarchy_friendly_path: sys.TestMacros #}
```

will only return Countries at this hierarchy node.

For more details on this parameter, refer to the topic Macro Syntax to Filter by Meta properties.

The SELECT-FROM-WHERE macros can also take additional filter parameters that restrict results:

- | direction: [up|down|local|parent|below|above|fulltree]
- | device: [pkid of device]
- | ndl:[pkid of ndl]
- | limit:[number]
- | skip:[number]
- | title:[character]

The *direction* option can be added to return values relative to the current hierarchy position. The default direction is *down*:

- direction:up Upwards. Include current hierarchy.
- direction:down Downwards. Include current hierarchy.
- direction:local: On this level only. Include current hierarchy.

- direction:parent Parent only. Exclude current hierarchy, in other words, search the parent as local.
- direction:below Downwards. Exclude current hierarchy.
- direction: above Upwards. Exclude current hierarchy if current hierarchy is not top (sys).

This is the *default* hierarchy search result restriction if no *direction* option is specified.

• direction:fulltree - Upwards (up) and Downwards (down) from the current hierarchy. Allows for a full hierarchy search.

It is recommended to use a *direction* option in a list macro without a WHERE clause, for example:

```
{ # data.Countries.* | | direction:up #}
```

In a 'SELECT-FROM-WHERE'-type macro, a single bar indicates the direction, for example:

```
{{ data.Countries | iso_country_code:AUS | direction:up }}
```

If used in other macro types, a double bar is used for parameters, for example:

```
{ # data.SiteDefaultsDoc.defaultcucphonesystem || direction:local #}
```

When traversal is up or above, results will be ordered starting with ones at the lowest hierarchies. Otherwise, results will be ordered starting with the ones at the highest hierarchies. Results at the same hierarchy will be in arbitrary order. Also refer to the optional *to* specifier below.

Added to the direction option is:

• an optional *limit* specifier. When used, the results returned by a list comprehension will be limited to the specified count, for example:

```
{# data.test_user.name || direction:above,limit:2 #}
```

This will return the first two names of data/test_user instances at the closest ancestors.

By default, for the following filter specifiers values apply to lists if they are not present:

- skip (default: 0) skip over a number of values before listing
- limit (default: 2000) number of values to return in the list

So, if the first list macro was:

then the second batch of results can be obtained by:

```
{# data.test_user.name || skip:2000,limit:2000 #}
```

• an optional *to* specifier to restrict the *direction:up* or *direction:down* specifier to a specified hierarchy, for example:

```
{# data.Countries.* || direction:up,to:Customer #}
```

This example will restrict the search upwards up to the Customer hierarchy.

```
{ # data.Countries.* || direction:down,to:Site #}
```


This example will restrict the search downwards up to the Site hierarchy.

Valid hierarchy values for to: are:

- System
- Hcs
- Provider
- Reseller
- Customer
- IntermediateNode
- Site
- LinkedSite

All data is returned in the case of incorrect spelling or invalid hierarchy levels.

Example showing query results:



If a list macro is used to provide a list of input values on the GUI, note that custom values are permanently allowed. This means that a custom value can be entered in the GUI input. Adding a GUI rule on the GUI form that sets an object property attribute "Allow Custom Values" to false, will not affect this functionality.

In addition, a title filter can be applied if the *SELECT-FROM* query is for a string to only return values matching its value, with a regular expression, for example:

```
{ # data.Countries.country_name || title:.*a$ #}
```

returns:

```
[
"Australia",
"Canada",
"China",
"Saudi Arabia",
"South Africa",
"United States of America"
]
```

Device option:

A device or ndl (Network Device List) pkid can be specified to restrict a query, for example, assume a named macro MY_CUCM_PKID_150:

```
{{ data.CallManager.__pkid | host:172.29.248.150,port:8443 }}
```

then we can select from the specified device as follows:

In a GUI Rule, [and] indicate references to values in the current usage context of the GUI Rule if the macro is added as a **Value** to the GUI Rule.

A GUI rule **Action** can also have an API call as its **Source**. The references are current context hierarchy pkid's or to field attribute names in the WHERE section of SELECT FROM WHERE-type macros - enclosed in square brackets [].

For example:

The syntax in a GUI Rule for a Wizard also uses [], in the format [stepData.STEPNAME.ATTRIBUTE], for example:

```
[stepData.SubscriberType.role]
```

9.2.5. Macro Nesting

To nest macro calls, create a named macro. Nesting inside macros is not supported.

For example, the following incorrect macro:

```
(( fn.list_in Kit, {# fn.split {{ fn.one device.ldap.user.streetAddress |
    sAMAccountName:bjones }} #} == True))
```

should be split up into named macros:

· macro: LDAP USER

```
{{ fn.one device.ldap.user.streetAddress | sAMAccountName:bjones }}
```

macro: LDAP USER ADDRESS LIST

```
{# fn.split macro.LDAP_USER #}
```

So the correct macro usage should be:

```
(( fn.list_in Kit,macro.LDAP_USER_ADDRESS_LIST == True))
```

9.2.6. Macro Syntax to Filter by Meta Properties

Macro results can also be filtered by the meta data of a resource.

A typical resource instance has associated meta data, for example:

```
meta: {
   title: "Australia - AUS"
   cached: true
   tags: [0]
   schema_version: "0.1.5"
   summary: "true"
   references: {...}-
   actions: [...12]-
   model_type: "data/Countries"
   path: [2]
   summary_attrs: [...3]-
   business_key: {...}-
   tagged_versions: [0]
}
```

The following macro fields are supported to filter by these properties:

```
__meta.business_key__meta.model_type__meta.schema_version__meta.system_resource
```

• __meta.tags

• __meta.title_format

• __meta.uri

• __meta.version_tag

The macro fields can be combined with model attribute names in a comma separated, for example:

```
{ # data.Countries.country_name,__meta.schema_version | country_name:Australia #}
```

Output:

As a further example: if the <code>system_resource</code> is set in the <code>meta</code> section of the resource, then the following macro can be used:

```
{ # data.ConfigurationTemplate.name | __meta.system_resource: true #}
```

The output is all the Configuration Template names where it is a system resource:

```
[
  "AddFeature_Attributes_View",
  "AddFeature_DMM",
  "AddFeature_DOMM_DM",
  "AddFeature_PKG",
  "AddFeature_PWF_Add",
  "AddFeature_PWF_Add_DM",
  "AddFeature_PWF_Del",
  "AddFeature_PWF_Del_DM",
  "AddFeature_PWF_Mod",
  "AddFeature_PWF_Mod,
  "AddFeature_PWF_Mod_DM",
  "AddFeature_PWF_Mod_DM",
  "AddFeature_PWF_Mod_DM",
  "AddFeature_SelectModels_View",
  "AddWizard_GuiRules"
]
```

For devices, the following are examples of macros that are available for the device NDL:

```
__device_meta.ndl.name
__device_meta.ndl.data/CallManager.pkid
```

9.3. Macro Functions

9.3.1. Macro Function Syntax

Macro functions have the format: fn.<function_name> For an alphabetical list of macro functions, refer to the Index.

If a macro function take more than one argument, these are comma-separated.

Important: While many of the functions can take parameters separated by commas and also white space, it is recommended to *use only a comma* to separate parameters.

For example, use the parameter separator as follows:

```
{{ fn.containsStartsWith aaa,aaaffccffdd }}
```

and not with a space, as in:

```
{{ fn.containsStartsWith aaa, aaaffccffdd }}
```

A null parameter is indicated by no value following a comma or between commas, for example:

```
{{ fn.cucm_get_line_details 4025,,is_line_shared }}
```

9.3.2. Numeric Functions

- fn.is_int: Return true or false if the parameter is an integer or not.
- fn.zeropad: Left pad a given number with zeros up to a given pad number.

Example	Output
{{fn.zeropad 123,6}}	000123

• fn.minval: For integers, return the minimum value of a provided list.

Example	Output
{{fn.minval 2,3,130,1,30}}	1

• fn.maxval: For integers, return the maximum value of a provided list.

Example	Output
{{fn.maxval 2,3,130,1,30}}	130

· fn.add: Add two integers.

Example	Output
{{fn.add 2,3}}	5

• fn.subtract: Subtract two integers.

Example	Output
{{fn.subtract 2,3}}	-1

• fn.multiply: Multiply two integers.

Example	Output
{{fn.multiply 2,3}}	6

• *fn.divide*: Divide two integers.

Example	Output
{{fn.divide 20,10}}	2

9.3.3. String Functions

- fn.is_string: Return true or false if the parameter is a string or not.
- fn.index: Return the i'th item of an iterable, such as a list or string.

Example	Output
{{ fn.index 'foo bar baz',5 }}	'b'

• fn.mask: Return a mask of (length + modifier) instances of char.

Example	Output
{{ fn.mask X,2,3 }}	xxxxxx

• fn.length: Return the length of a string.

Example	Output
{{ fn.length This is a valid string }}	22

• fn.split : Split a string by delimiter, returning a list.

Example	Output
{# fn.split foo:bar:baz,: #}	['foo', 'bar', 'baz']

• fn.join: Join a string by delimiter. If no delimiter is provided, the list is returned as a single string.

Example	Output
{{ fn.join 1234,: }}	1:2:3:4
{{ fn.join 1234 }}	1234

• fn.title: Return a string in title case.

Example	Output
{{ fn.title 'foo bar baz' }}	'Foo Bar Baz'

• *fn.upper*: Return an uppercase version of the input string.

Example	Output
{{ fn.upper somevalue }}	SOMEVALUE

• *fn.lower* : Return a lower case version of the input string.

Example	Output
{{ fn.lower SOMEVALUE }}	somevalue

• fn.contains: Return true or false if string is contained in another.

Example	Output
{{ fn.contains needle, haystack }}	false
{{ fn.contains hay, haystack }}	true
((fn.contains Kit,1234 Kit Creek == True))	true

• fn.sub string: Return the substring of a string from a start to an end position.

Example	Output
{{ fn.sub_string haystack, 0, 2 }}	hay
{{ fn.sub_string haystack,7,7 }}	k

• fn.containsIgnoreCase: Return true or false if string is contained in upper- or lower case.

Example	Output
{{ fn.containsIgnoreCase aaa,bbbaAaccc }}	true

Example	Output
Input	
{"input": {"UserName": "user@host.org"} →}	user@host.org
Function call	
<pre>((fn.containsIgnoreCase Host,input.</pre>	

• fn.containsStartsWith: Return true or false if source string is the start of target string.

Example	Output
{{ fn.containsStartsWith aaa,aaaffccffdd }}	true

• fn.containsStartOf: Return true or false if start of source string is target string.

Example	Output
{{ fn.containsStartOf ffnnccgg,ffnn }}	true

fn.regex_match: Return true or false if the regular expression matches the start of target string.

Example	Output
{{ fn.regex_match a,ab }}	true
{{ fn.regex_match a\$,ab }}	false
{{ fn.regex_match \d+,abc555 }}	false
{{ fn.regex_match \d+,555abc }}	true

• fn.isexactly: Return true or false if source string is exactly the same as target string.

Example	Output
{{ fn.isexactly source1, source1 }}	true

• fn.replace: Replace target substring for source substring in source string.

Example	Output
Note: no spaces between commas.	
{{ fn.replace dddddAAAc,AAA,FFF }}	dddddFFFc

• fn.validate_name: Return true or false if the string as well as its stripped content (default white space removed) exists, i.e. is then more than 0 characters.

Example	Output
{{ fn.validate_name }}	false
{{ fn.validate_name a }}	true

• fn.fix_non_ascii: Given a string containing non-ASCII characters, this function applies 3 steps of processing and returns a string with all non-ASCII characters mapped to ASCII characters.

The first step can be controlled by the optional "from" and "to" characters parameter pair that return a string with "from" characters replaced with "to" characters. This allows for control over the replacement.

The 3 steps are carried out in the following sequence:

1. Map characters in the given string by using the corresponding characters in the "<from>,<to>" string parameter pair.

- If the parameters are not added, this step is skipped.
- If it is required to have control over the mapping of non "accented" characters (see step 2), then this default mapping can be done by providing the "<from>,<to>" string parameter pair.
- 2. Map all "accented" (accent, circumflex, diaeresis, etc.) non-ASCII characters to ASCII characters.
- 3. Map all remaining non-ASCII characters with the underscore character: _.

For example:

```
- string = Test Nón Asciï
- <from>,<to> = ï, G
- result = _est Non AsciG
step 1: from = ï is replaced with to = G.
step 2: accented ó is replaced with o
step 3: T is a remaining non-ASCII character and replaced with _.
```

In the above example, the \mp is not an "accented" character and was therefore not mapped in step 2. If the preference is not to have the \mp character mapped to the underscore character, then this character could be included in the "<from><,<to>" string parameter pair.

Example	Output
{{ fn.fix_non_ascii 'Têst Nón Asciïæ mapping',sæ,Ga } →}	'TeGt Non AGciia mapping'
{{ fn.fix_non_ascii 'Test Nón Asciï' }}	'_est Non Ascii'

• fn.fix_username: Given a string of characters, return the string with a replacement character: – for any character not in the following range: a-zA-Z0-9._-.

A Unified CM Remote Destination name is an example where such a string is required.

Example	Output
{{ fn.fix_username O'Reilly }}	O-Reilly

9.3.4. List Functions

- fn.group_by_larger_than_count: Returns either a list of instance names or dictionary instance names with count values, given parameters:
 - model type
 - model attribute
 - greater than an input numeric value of the attribute
 - specified search direction in hierarchy: up or down

Example		Output
Context hierarchy: sys, list of more Countries, search down - display as dictionary:	than 1 of iso_country_code in data/	[{
{{ fn.group_by_larger_than_count	<pre>data/Countries, iso_country_code, down,1,dict }}</pre>	"iso_country_ →code": "AUS", "count": 2
- display as list:		{
{{ fn.group_by_larger_than_count	<pre>data/Countries, iso_country_code, down,1,list }}</pre>	"iso_country_ code": "CHN", "count": 2 }
		["AUS", "CHN"]

- fn.is_list: Return true or false if the parameter is a list or not.
- fn.list_index: Return a specified item from a list. Zero is the first item.

Example	Output
{{fn.list_index 2,data.Countries.country_name}}	"Canada" if this is the third item.

• fn.list_index_item: Return the position of item in list.

Example	Output
MACRO1={# fn.sequence 40,43 #}	2
{{ fn.list_index_item 42, macro.MACRO1 }}	

• fn.list_count: Return the number of items in a list. Note that if the list is known and empty, the count is 0, but if the list is not known, then the count is 1, because the returned message string count is 1.

Example	Output
{{fn.list_count data.Countries}}	25 if the list has 25 items.
{{fn.list_count input.does_not_exist}}	0
{{fn.list_count non_existant_namespace.does_not_exist}}	1

• fn.list_count_item: Return the number of times item is in a list.

Example	Output
MACRO1={# data.Countries.international_access _prefix #}	19
{{ fn.list_index_item 00, macro.MACRO1 }}	

• fn.list_in: Return true or false if item is in a list or not.

Example	Output
{{fn.list_in 'AUS',data.Countries.iso_country_code}}	true
{{fn.list_in 'AUZ',data.Countries.iso_country_code}}	false

• fn.list_contain: Return true or false if item is a substring of an input context or is in a list or not.

Example	Output
	true
"input": {	
"AUS",	true
"BHR"	
],	
"key": "aaAUZa"	
}	
}	
{{fn.list_contain 'AUS',input.list }}	
{{fn.list_contain 'AUZ',input.key }}	

• fn.list_append: Returns a list with item appended.

Example	Output
MACRO1={# fn.sequence 40,43 #}	['40', '41', '42', '43',
{{fn.list_append 999,macro.MACRO1 }}	'999']

• fn.list_pop: Return the last item of the list.

Example	Output
MACRO1={# fn.sequence 40,43 #}	"43"
{{fn.list_pop macro.MACRO1}}	

• fn.list_insert: Return a list with item inserted at position.

Example	Output
MACRO1={# fn.sequence 40,43 #} {{fn.list_insert 1,999,macro.MACRO1 }}	['40', '999', '41', '42', '43']

• fn.list_insert_no_dup: Return a list with item inserted at position and all duplicates ignored.

Example	Output
MACRO1={ # fn.sequence 40,43 #}	['40','41', '42','43',
MACRO7={# fn.sequence 39,41 #}	'42','43',
{{fn.list_insert_no_dup macro.MACRO1, macro.MACRO7}}	

• fn.list_remove: Return a list with all instances of item or list of items removed.

Example	Output
MAC1={# fn.sequence 40,43 #} MAC7={# fn.sequence 40,41 #} MAC3={{fn.list_insert 1,43,macro.MAC1 }}	['40','41', '42']
{{fn.list_remove 43, macro.MAC3 }}	['42','43']
{{fn.list_remove macro.MAC7, macro.MAC1 }}	

• fn.list_remove_dup_dict: Given a list of dictionaries, a sort key and an optional sort direction, return a list with the duplicate entries removed, sorted by the specified sort direction or if not specified, sorted in ascending order.

```
Example
                                                                           Output
                                                                           { "dupl":
  "input": {
                                                                            [
   "dupl":
                                                                                 "country_
    {
                                                                           ⇔name":
        "country_name": "Canada",
                                                                           → "Canada",
        "iso country code": "CAN"
                                                                                 "iso_
                                                                           →country_code
    },
                                                                           →": "CAN"
        "country_name": "China",
                                                                            },
        "iso_country_code": "CHN"
                                                                             {
                                                                                 "country_
    },
                                                                           ⇒name": "China
        "country_name": "China",
                                                                           " ,
        "iso_country_code": "CHN"
                                                                                 "iso_
                                                                           →country_code
    },
                                                                           → ": "CHN"
        "country_name": "Switzerland",
                                                                             },
        "iso_country_code": "CHE"
                                                                                 "country_
    }
                                                                           ⇔name":
  1
                                                                           → "Switzerland",
}
                                                                                 "iso_
                                                                           ⇔country_code
{{ fn.list_remove_dup_dict input.dupl,
                                                                           → ": "CHE"
   country_name }}
                                                                             }
                                                                            ]
                                                                           }
```

• fn.list remove dup: Return a list with all instances of item or list of items removed, including duplicates.

Example	Output
Given the following list is the result of the regex for iso_country_code:	
<pre>{# data.Countries.iso_country_code iso_country_code:/AU/ #}</pre>	['AUS','SAU', 'AUS','AUS']
	['AUS','SAU']
<pre>{# fn.list_remove_dup data.Countries.iso_country_code / iso_country_code:/AU/ #}</pre>	

fn.list_remove_nulls: Return a list with all null instances in a list of items removed.

Example	Output
<pre>{"pwf": { "my_list": [1, null, 2,"test", 3, null] } }</pre>	[1,2,"test",3]
{{ fn.list_remove_nulls pwf.my_list }}	

• fn.list_reverse: Return a list that is the reverse of a given list.

Example	Output
<pre>MACRO1={# fn.sequence 40,43 #} {{fn.list_reverse macro.MACRO1}}</pre>	['43','42', '41','40']

• fn.list_extend: Return a list that is an extension of list 1 with list 2.

Example	Output
MACRO1={ # fn.sequence 40,43 #}	['40', '41',
MACRO9={ # fn.sequence 50,52 #}	'42', '43', '50', '51', '52']
{{fn.list_extend macro.MACRO1, macro.MACRO9 }}	22]

• fn.list_extend_no_dup: Return the concatenation of list1 and list2, ignoring duplicates.

Example	Output
MACRO1={# fn.sequence 40,43 #}	['40','41', '42','43',
MACRO8={ # fn.sequence 42,45 #}	'42', '43',
{{fn.list_extend_no_dup macro.MACRO1, macro.MACRO8 }}	

• *fn.sequence*: Return a sequence of numbers running from the first value to the second value, optionally padded with zeroes to be the length of a third value.

Example	Output
{# fn.sequence 40,43 #}	['40','41', '42','43']
{# fn.sequence 110,100,4 #}	['0110','0109', '0108', '0107','0106', '0105','0104', '0103','0102', '0101','0100']

• fn.list_set_symdiff: Given two lists as input, return the list of items that are not common to both lists.

Example	Output
MACRO1={# fn.sequence 40,43 #} MACRO2={# fn.sequence 41,45 #}	['40','44','45 ↔']
{{ fn.list_set_symdiff macro.MACRO1, macro.MACRO2 }}	

• fn.list_sort: Return a sorted list; by ascending (A) or descending (D) order.

Example	Output
MACRO1={ # fn.sequence 40,43 #}	['43','42',
((fr. list sout was magnet D))	'41','40']
{{fn.list_sort macro.MACRO1,D}}	['43','42',
	'41','40']
{{fn.list_sort macro.MACRO1,Descending}}	[10110] 10100]
	['0110','0109',
MACRO5={ # fn.sequence 110,108,4 #}	
	['0108','0109',
{{fn.list_sort macro.MACRO5,A}}	0110

• *fn.one*: Return a single result from a list. This is used to convert a single element list to a string.

If fn.one is called with a string, it returns the string unchanged. The string can be a macro that might get the value of another attribute from a context, such as input.some_variable.

Example	Output
{{fn.one data.Countries.iso_country_code	A single result, e.g. 'DEU'
<pre>emergency_access_prefix:'112'}}</pre>	'abc'
{{fn.one abc}}	

• fn.as_list: Return a string result as a list. If fn.as_list is called with a string, it returns a list. Again, abc could be a macro that resolves to the value of an attribute in its context.

Example	Output
{{fn.as_list data.Countries.country_name country_name:'China'}}	['China']
{{fn.as_list abc}}	['abc']

• fn.list_empty: Returns an empty list

Example	Output
{{fn.list_empty}}	[]

• fn.list_set_intersect: Given two lists, return the intersection as a list.

Example	Output
MACRO1={# fn.sequence 40,43 #} MACRO2={# fn.sequence 41,42 #}	['41','42']
{ # fn.list_set_intersect macro.MACRO1, macro.MACRO2 #}	

• fn.list_set_union: Given two lists, return the union as a list.

Example	Output
MACRO1={# fn.sequence 40,43 #} MACRO2={# fn.sequence 41,45 #} {# fn.list_set_union macro.MACRO1, macro.MACRO2 #}	['40','41', '42','43', '44','45']

• fn.list_set_left: Given two lists, return a list of items in the left list only.

Example	Output
MACRO1={# fn.sequence 40,43 #} MACRO2={# fn.sequence 41,45 #}	['40']
{ # fn.list_set_left macro.MACRO1, macro.MACRO2 #}	

• fn.list_set_right: Given two lists, return a list of items in the right list only.

Example	Output
MACRO1={# fn.sequence 40,43 #} MACRO2={# fn.sequence 41,45 #}	['44','45']
{ # fn.list_set_right macro.MACRO1, macro.MACRO2 #}	

• fn.list_filter_fields: Given a model name, two field names, hierarchy PKID and a list of field values from one of the fields, return the list of values from the other field. The hierarchy PKID parameter must be passed in as a PKID of the hierarchy node.

• fn.flatten_list_of_lists: Given a list of lists, return a single, flattened list.

```
Example
                                                                               Output
 {
                                                                                 "AAA",
     "input": {
          "args": [
                                                                                 "BBBB",
                                                                                 "CCCC",
              [
                   "AAA"
                                                                                 "DD"
              ],
                                                                               ]
              [
                   "BBBB",
                   "CCCC"
              ],
              [
                   "DD"
              ]
         ]
 }
{ # fn.flatten_list_of_lists input.args #}
```

• fn.flatten_nested_lists: Given a list of scalars and lists (which could have different levels of nesting), return a single, flattened list.

```
Example
                                                                            Output
 {
     "input": {
                                                                              "77174011",
         "args": [
                                                                              "77174021",
             "77174011",
                                                                              "77174080",
                                                                              "55555",
              "77174021",
                                                                              "1",
              "77174080",
                                                                              "12345"
                                                                            ]
                "55555",
                "1",
              ]
              ],
              "12345"
         ]
     }
 }
{{ fn.flatten_nested_lists input.args }}
```

• fn.modulo_list: Given a list and divisor, return a modulo list: list items that leave no remainder after divided. The input list is typically a directory number list and the divisor is an E164 range.

• fn.get_tvpair_list: Given an input list of dictionaries containing repeated pairs of equal type and a title-value mapping of these pairs, return a list of objects of these pairs where the pairs are mapped to title and value pairs that can for example be shown in a GUI rule in a choices drop-down list on a GUI form.

```
Example
                                                                          Output
                                                                           [
  "input": {
   "dataList" = [
                                                                               "value":
         {
                                                                           "10",
             "timeZoneCode": "10",
                                                                               "title":
             "timeZoneName": "Africa/Bissau"
                                                                           →"Africa
         },
                                                                           →Bissau"
         {
             "timeZoneCode": "100",
                                                                            },
             "timeZoneName": "America/Noronha"
                                                                                 "value":
         },
                                                                           "100",
         . . .
                                                                                "title":
                                                                           →"America
      1
   }
}
                                                                           →Noronha"
                                                                            },
{{ fn.get_tvpair_list input.dataList,
                                                                            . . .
   title:timeZoneName, value:timeZoneCode }}
                                                                          ]
```

9.3.5. Model Filters

Model filters are set up as instances of data/ModelFilterCriteria with the following properties:

Property	Description
name	The name is used by the macro function
type	The model on which the filter is applied
criteria.attribute	attribute name of the applied model
criteria. conditional_operator	optional: takes a boolean AND, OR NOT to apply to next criteria
criteria.condition	see list below for options
criteria.value	filter condition value of attribute to check against

criteria.condition can be:

Field Name	Description	GUI Field Name
equalsIgnoreCase	Case insensitive exact match.	Equals
isexactly	Case sensitive exact match.	Equals Exactly
containsIgnoreCase	Case insensitive substring match.	Contains
contains	Case sensitive substring match.	Contains Exactly
regex_search	Regular expression	Regex Search

The macro functions take a Model Filter name as input.

Match Model Filter Criteria

• fn.match_model_filter_criteria: Given input context data and a model filter criteria instance name, return a dictionary of output that contains a result.

Syntax: {{fn.match_model_filter_criteria <input-data>,<filter-name> }}

In the Model Filter Criteria:

- The filter-name, individual criteria are evaluated to a value: True or False
- The filter-name, criteria are combined with a conditional_operator (e.g. boolean AND)
 to yield the result value: true or false
- Filters will evaluate each of the criteria for the specified type.

Below is an instance of data/ModelFilterCriteria for type is device/msgraph/MsolUser:

(continues on next page)

(continued from previous page)

Example	Output
<pre>data/ModelFilterCriteria with name is "Multi Level Filter" as in exam- ple above. Input context data contains: {"user_details": { City": "Cape Town", Address": "City of Bellville '', } Function call: {{fn.match_model_filter_</pre>	<pre>{"output": "[City] 'Cape Town' isexactly 'Cape Town' =</pre>
ocriteria user_details.City, 'Multi Level Filter' }}	

Instances that match Model Filter Criteria

• fn.instances_match_model_filter_criteria:

Syntax:

 $\{\{fn.instances_match_model_filter_criteria < model filter criteria name>, < field name>, < direction>\}\}$

Given:

- model filter criteria name: name of data/ModelFilterCriteria
- field name: a field name from the model filter criteria instance type. The match results will be a
 list of this field, with the list called model_match_list.

The model filter can contain one or multiple criteria operating on the type model - with multiple criteria also combined with a boolean conditional operator.

 direction: optional search direction. Default is above, which is upwards and excludes the current hierarchy if it is not the top hierarchy.

Return:

- Input model filter and query details and result model_match_list.

Example macro:

```
{{ fn.instances_match_model_filter_criteria CityTulsa,username,up }}
```

Example output:

```
"model_filter_criteria_field": "username",
"model_filter_criteria_name": "CityTulsa",
"hierarchy": "nnf525b7e04a4a001480cfnn",
"model_filter_criteria": {
    "usage": "Test",
    "type": "data/User",
    "name": "Demo Criteria City = Tulsa",
    "criteria": [
        {
            "attribute": "city",
            "condition": "isexactly",
            "value": "Tulsa"
        }
},
"model_filter_macro": "{# data.User.* || direction:up #}",
"model_match_list": [
    "IsaiahL@tobuild.onsoft.com",
    "PattiF@tobuild.onsoft.com",
    "LidiaH@tobuild.onsoft.com",
    "pietman@tobuild.onsoft.com",
    "HenriettaM@tobuild.onsoft.com"
],
"model_filter_criteria_direction": "up",
"hierarchy_friendly_path": "sys.hcs.CS-P.CS-NB.RND.East.AlterLake"
```

9.3.6. Model Instance Filters (MIF) from CSV File

fn.generate filters: given input parameters:

- An uploaded CSV filename: the filename of a file uploaded to data/File, e.g. using the File Management menu.
- Model Instance Filter (MIF) name: a name for an instance of data/ModelInstanceFilter
- A model type to apply the MIF to, e.g.: device/msteamsonline/CsOnlineUser.
- A filter type: inclusion or exclusion (if not provided as parameter, default is inclusion)

create a MIF (data/ModelInstanceFilter) instance at the hierarchy where the function is run, containing the data in the CSV file. The MIF can then be selected in data syncs at the relevant hierarchy.

Syntax: {{ fn.generate filters < InputFile.csv>, < Output MIF Name>, < input model>[, < filter type>] }}

Note: The MIF model_parent will be the parent of the input model. For example, if the input model is device/msteamsonline/CsOnlineUser then ``device/msteamsonline is the model_parent.

The CSV file format is interpreted as follows:

• Header row: attribute(s) of <input model> (attr_name)

2nd row onwards: value(s) which have equals match to attribute(s)

Note:

- Each value row in the CSV file represents a model filter instance with value equals the attr_name. Filter instances are combined with logical OR. Refer to the *Model Instance Filter* topic in the Core Feature Guide.
- If the CSV file contains more than one column, i.e multiple attributes and values, then the attr_filters list in the MIF instance will combine these with a logical AND. Refer to the *Model Instance Filter* topic in the Core Feature Guide.

Example

For example, a CSV file (InputFile.csv) uploaded using the File Management menu at hierarchy sys.hcs.CS-P.VOSS-OPS.VOSS with a single attribute UserPrincipalName:

```
UserPrincipalName
Dusty.Moyer@visionoss-dev.info
Earl.Moore@visionoss-dev.info
```

then the macro function run at hierarchy sys.hcs.CS-P.VOSS-OPS.VOSS called

```
{{ fn.generate_filters InputFile.csv,MSOL_MIF,device/msteamsonline/
CsOnlineUser }}
```

will create MIF instance containing:

```
"meta": {},
"resources": [ {
   "meta": {
     "model_type": "data/ModelInstanceFilter",
     "pkid": "...",
     "schema_version": "...",
     "hierarchy": "sys.hcs.CS-P.VOSS-OPS.VOSS",
     "tags": []
   },
   "data": {
     "filter_type": "inclusion",
     "name": "MSOL_MIF",
     "model_parent": "device/msteamsonline",
     "model_filters": [
       { "model_type": "device/msteamsonline/CsOnlineUser",
        "attr_filters": [
          { "attr_name": "UserPrincipalName",
           "condition": "equals",
           "value": "Dusty.Moyer@visionoss-dev.info"
       { "model_type": "device/msteamsonline/CsOnlineUser",
        "attr_filters": [
          { "attr_name": "UserPrincipalName",
           "condition": "equals",
           "value": "Earl.Moore@visionoss-dev.info"
          } ] }
     ] }
```

(continues on next page)

(continued from previous page)

```
} 1
}
```

9.3.7. Rule Filter Functions

The "filter by rule" function returns a list of resource instance data for a given model type. The schema of the model type in question must define a rules object of the form:

```
{
    'rules': {
        'hierarchy_types': [<list of data/HierarchyNodeType business keys>]
    }
}
```

The model data/Role is one example of such a model type. Filtering is applied using the current hierarchy context or else based on an explicit hierarchy type name.

Macro format:

Argument descriptions:

<rule name>: The name of the rule being used to filter results. Supported values: hierarchy types

<model type>: The model type of the instances to be filtered.

<direction>: The search direction of the results. Possible values are:

- all search at current hierarchy, ancestors, and descendants.
- up search at current hierarchy and ancestors.
- · down search at current hierarchy and descendants.
- local search at current hierarchy only.

<a tribute path to return>: [optional] The path dot (.) delimited path to a single attribute to return.

- If not specified the returned result will contain a list of objects.
- If specified the returned result will contain a list the given attribute.
- Must be "null" if this field is not required, while <hierarchy type name> is supplied.

hierarchy type name: [optional] The name of the hierarchy type to filter by. This will be looked up from the current hierarchy going up.

Examples:

```
{{ fn.filter_by_rule hierarchy_types,data/Role,up,name,Customer }}
```

Returns all the names of the roles that are permitted at "Customer" hierarchy type. Lookup is done from the current hierarchy upwards.

```
{{ fn.filter_by_rule hierarchy_types,data/Role,up,null,Customer }}
```

Returns full instance data of the roles that are permitted at "Customer" hierarchy type. Lookup is done from the current hierarchy upwards.

```
{{ fn.filter_by_rule hierarchy_types,data/Role,up,name }}
```

Returns all the names of the roles that are permitted at the hierarchy type of the current hierarchy context. Lookup is done from the current hierarchy upwards.

```
{{ fn.filter_by_rule hierarchy_types,data/Role,up }}
```

Returns full instance data of the roles that are permitted at the hierarchy type of the current hierarchy context. Lookup is done from the current hierarchy upwards.

9.3.8. Role at Allowed Hierarchy Function

Given a hierarchy friendly path as a function parameter, the fn.get_admin_roles_allowed_at_hn function returns the list the roles allowed for admins at the given hierarchy friendly path.

For example, given a context hierarchy (site):

```
sys.hcs.CS-P.CS-NB.AAAGlobal.LOC001
```

and evaluating the function:

```
{{ fn.get_admin_roles_allowed_at_hn fn.hierarchy_friendly_path }}
```

the output of this macro will for example be:

```
[
   "LOC001SiteAdmin",
   "LOC001SiteOper"
]
```

Given a context hierarchy (reseller):

```
sys.hcs.CS-P.CS-NB
```

the output of this macro will for example be:

```
[
    "CS-NBCustomerAdministrator",
    "CS-NBCustomerOperator",
    "CS-NBResellerAdministrator",
    "CS-NBResellerOperator",
    "CS-NBSiteAdmin",
    "CS-NBSiteOper"
]
```

9.3.9. Filter Role Functions

Given a list of user roles as a function parameter, the fn.filter_roles_by_user_access_profile function returns the list of roles with permissions equal to or less than that of the user executing the function.

For example, given a list of roles:

```
macro.ALL_Roles
[TestRole01, TestRole02, TestRole03]
```

where TestRole01 has the least permissions and TestRole03 has the most permissions. If the request user is assigned with TestRole02, and executes the following macro:

```
{{ fn.filter_roles_by_user_access_profile macro.ALL_Roles }}
```

The ouput of this macro will be

```
[TestRole01, TestRole02]
```

Note: This filter will only have an effect if the setting in data/Settings called Additional Role Access Profile Validation is enabled (check box is enabled).

Refer to the settings topic called Additional Role Access Profile Validation.

9.3.10. Macro Evaluate Function

• fn.evaluate: Evaluate the string using the macro interpreter.

The string can be a macro and can also contain macro names to be evaluated.

The purpose of the function is so that we can save data as a macro and then evaluate it when we read it again.

For example, we may store default values in a data model (e.g. SiteDefaultsDoc) that may also refer to existing macros. An attribute of the model - with name: defaulthppt can for example have the value (The macro evaluates to a site name):

```
Site-{{macro.SITENAME}}
```

Then, a workflow Configuration Template at a Site can be a set to a value that references the model and that uses fn.evaluate:

```
"defaulthppt": "{{ fn.evaluate data.SiteDefaultsDoc.defaulthppt }}",
```

Not:

```
"defaulthppt": "Site-{{macro.SITENAME}}",
```

The tables below provide further examples.

Where self.x specifies an attribute of a model, with the value:

```
{ # data.Countries.iso_country_code | country_name:'South Africa' #}
```

Example	Output
Then:	
{ # fn.evaluate self.x #}	['ZAF']

Where MACRO1 is:

```
{{ data.Countries.emergency_access_prefix | iso_country_code:FRA }}
```

Where self.x is:

Example	Output
Then:	Codes with same prefix as
{# fn.evaluate self.x #}	FRA:
	['DNK','HKG',
	'FRA','DEU',
	'IND','ITA',
	'NLD','NZL',
	'SAU', 'ESP',
	'SWE', 'ZAF',
	'CHE','TUR']

9.3.11. CUCM and Device Functions

• fn.get_cucms_associated_via_ndlr: Get all CUCM servers from NDLR (Network Device List Reference) on current the site. The function must be called from a site hierarchy.

Example	Output
hierarchy: sys.hcs.CS-P.CS-NB. Geologic.EMEA.Paarl	
{# fn.get_cucms_associated_via_ndlr →#}	10.110.11.131

• fn.get_cucm_bkeys_associated_via_ndl: Get all CUCM server business keys from NDL (Network Device List) on current the hierarchy. A business key is a list of: IP, port, hierarchy.

Example	Output
hierarchy: sys.hcs.CS-P	
{# fn.get_cucm_bkeys_associated_via_ →ndl #}	["[\"10.110.11.131\", \"8443\", \"hcs.CS-P.CS-NB.AAAGlobal\"]"]

• fn.cucm_get_line_details: Specify the line pattern and routePartitionName and use the Macro Evaluator function to view the line parameters for the specified line.

To return the result for a single line parameter, append the required parameter to the end of the macro function, for example:

```
{{ fn.cucm_get_line_details 4025 }}
```

The macro can only be run at or below the hierarchy level of the Unified CM that is provisioned.

If no routePartitionName is specified, then only the line directory number pattern is searched for on the Unified CM:

```
{{ fn.cucm_get_line_details 4025, }}
```

In a multi-cluster environment with more than one device, then an additional optional parameter should be used to specify the Unified CM - its pkid. In this case, using the device parameter also requires that the all parameter be used if all parameters need to be returned.

Multi cluster example (for data/CallManager/57e709467677f0c9ca956f6f)

Example	Output
{{ fn.cucm_get_line_details	<pre>"is_line_shared": true, "remote_destination_profiles": ["RDP_vdevenr"], "device_profiles": ["UDP_vdevenr"], "phones": ["SEP002155D547F7", "SEP111122223333"]</pre>

Single cluster examples:

Example	Output
<pre>{{ fn.cucm_get_line_details 4025,VS-Corp-NewYork }}</pre>	<pre>"is_line_shared": true, "remote_destination_profiles": ["RDP_vdevenr"], "device_profiles": ["UDP_vdevenr"], "phones": ["SEP002155D547F7", "SEP111122223333"] }</pre>
<pre>{{ fn.cucm_get_line_details 4025,VS-Corp-NewYork, is_line_shared }}</pre>	true
<pre>{{ fn.cucm_get_line_details 4025,VS-Corp-NewYork, phones }}</pre>	SEP002155D547F7 SEP111122223333

• fn.get_endpoint_name

Given a set of gateway input parameters, return an endpoint name. The input parameters are ordered:

- 1. gateway product
- 2. gateway protocol
- 3. gateway name
- 4. gateway module
- 5. gateway slot (int)
- 6. gateway subunit
- 7. gateway subunit position (int)
- 8. gateway endpoint port (int)
- 9. gateway endpoint product

```
{{ fn.get_endpoint_name VG350 SCCP SKIGW11221111111_ → ANALOG 2 SM-D-48FXS-E-SCCP 0 46 → 'Analog Phone' }}

{{ fn.get_endpoint_name VG350 MGCP test1.com ANALOG 2 SM-D-72FXS 0 9 'Cisco MGCP_ → FXS Port' }}
```

· fn.get sccp endpoint name

Remains available as an alias for *get_endpoint_name* to support existing features. Given a set of gateway input parameters, return an endpoint name. The input parameters are ordered:

- gateway product
- 2. gateway protocol
- 3. gateway name
- 4. gateway module
- 5. gateway slot (int)
- 6. gateway subunit
- 7. gateway subunit position (int)
- 8. gateway endpoint port (int)
- 9. gateway endpoint product

```
{{ fn.get_sccp_endpoint_name VG350 SCCP SKIGW1122111111 ANALOG 2 SM-D-48FXS-E-SCCP 0 46 'Analog_ →Phone' }}
```

• fn.lines_from_hierarchy_devices

Given a hierarchy and device (one of Phone, Device Profile or Remote Destination Profile), return the list of patterns and routePartitionNames for the device at the hierarchy.

Example:

```
{{ fn.lines_from_hierarchy_devices sys.hcs.CS-P.OBCust.OBSite1 Phone }

{ "pattern": ["555555","710087"], "routePartitionName": [None, "Site-→CPT1"]}
}
```

· fn.default device

Given a hierarchy and device (or device and path to pkid), return the default device at the hierarchy according to the device in the Network Device List (NDL) of the hierarchy. Calling the function without a pkid path returns the entire object. If no default device is found, an empty string is returned.

Example:

```
{{ fn.default_device data/CallManager.

→pkid }}

{{ fn.default_device data/CallManager }

→}

"pkid": "59ccdc58dcdbfaa51eedbed9

→",

"model_type": "data/CallManager",

"uri": "/api/v0/data/CallManager/
→69cer80r903aa8b565784675

}
]
```

fn.device_meta

Can take 0, 1 or 2 parameters to return NDL data.

- If no parameters, the function should be called at a site hierarchy. Returns NDL object data (e.g. details of data/CallManager, data/UnityConnection)
- If 1 parameter, it must be the hierarchy: as friendly name or fn.hierarchy.
- If 2 parameters, hierarchy followed by comma, then object name and optionally dot and attribute (pkid example below)

Example:

```
{{ fn.ndl_device_meta fn.hierarchy,
                                          69cer80r903aa8b565784675
   ndl.data/CallManager.pkid }}
{{ fn.ndl_device_meta fn.hierarchy }}
                                              "ndl": {
                                                  "name": "NDL-GeoLogic-1",
                                                  "pkid":
                                           → "59ccdcd5303aa8b5657426ac",
                                                  "data/CallManager": {
                                                      "pkid":
                                          → "69cer80r903aa8b565784675",
                                                      "bkey": "[\"10.140.51.164\
                                          →", \"8443\", \"hcs.CS-P.CS-NB.
                                          →GeoLogic\"]"
                                                  "bkev": "[\"NDL-GeoLogic-1\", \
                                          →"hcs.CS-P.CS-NB.GeoLogic\"]",
                                                  "data/Hcmf": {
                                                      "pkid":
                                           → "59ccd953dc66faa51eeda8d5",
                                                      "bkey": "[\"10.140.51.156\
                                           →", \"8443\", \"hcs\"]"
                                                  },
                                                  "data/UnityConnection": {
                                                      "pkid":
                                          → "59ccdc8cb969f577e64fcc98",
                                                      "bkey": "[\"10.140.51.165\
                                           →", \"8443\", \"hcs.CS-P.CS-NB.
                                          →GeoLogic\"]"
                                                  }
                                              }
                                          }
```

fn.get_least_used_site_devicepool

Important: This function can only be run at a site and only searches locally, so no device selection is required.

Return the Unified CM DevicePool with the lowest phone count at the submitted site.

Example:

```
{{ fn.get_least_used_site_devicepool }} CulSil-CAT-Dallas-SRST-DP1
```

fn.generic_device_model_custom_operation

Used to get return values on custom operations for generic driver device models for use in a workflow context.

Given parameters:

- full generic driver device type, e.g. device/genericcucm/PbrMac
- operation_name: e.g. get_mac
- input_data: as dictionary, e.g. { "extension": "1094"}

return the value of the custom operation as a dictionary

Example:

9.3.12. Jabber Device Name Function

• fn.jabber_device_name: Given a Jabber device type string and a username, return a unique Jabber device name with prefix of the associated type. The maximum allowed total length is 15 characters.

Jabber device type strings and automatic prefixes:

- 'Cisco Dual Mode for Android': 'BOT'
- 'Cisco Jabber for Tablet': 'TAB'
- 'Cisco Dual Mode for iPhone': 'TCT'
- 'Cisco Unified Client Services Framework': 'CSF'

The function generates the device name in the following format:

<device type prefix><username hash><random number>

The total length of the generated devicename is 14 characters.

Note:

- Non-alphanumeric characters in usernames are replaced by zeros (0). Letters are capitalized.
- If the username is longer than 8 characters, it is truncated to 8 characters. Then the random number has a length of 3 numbers.

Example with username "D'Malleybazfrobbleverylongname": TCTD0MALLEY218

• If the username is shorter than 8 characters, all characters are used. The random number has a length to make up a total of 11 characters.

Example with username 'FOO': TCTF0000183752

• The generated name is checked against existing device names and the random number is regenerated until the name is unique.

Example	Output
<pre>{{ fn.jabber_device_name 'Cisco Dual Mode for iPhone', D'Malleybazfrobbleverylongname }}</pre>	TCTD0MALLEY218

9.3.13. Webex Teams Functions

fn.get webex teams user csv data specific user

Given a user's e-mail address as input, return the full comma-separated value (CSV) data for a specific Webex Teams user.

Input:

```
{{ fn.get_webex_teams_user_csv_data_specific_user user1@email.com }}
```

Returns:

```
User ID/Email (Required), Jabber with Webex Teams, Jabber Calling, UC Manager Profile,

→Contact Migration Required, Calling Behavior, Care Digital Channel,

user1@email.com, TRUE, TRUE, Profile 1, TRUE, CALL_WITH_APP_REGISTERED_FOR_CISCOTEL, TRUE
```

fn.get_webex_teams_user_csv_data_all_users

Return CSV data for all Webex Teams users.

Input

```
{{ fn.get_webex_teams_user_csv_data_all_users }}
```

```
User ID/Email (Required), Jabber with Webex Teams, Jabber Calling, UC Manager Profile, 
→Contact Migration Required, Calling Behavior, Care Digital Channel 
user1@email.com, TRUE, TRUE, Profile 1, TRUE, CALL_WITH_APP_REGISTERED_FOR_CISCOTEL, TRUE 
user2@email.com, TRUE, TRUE, TRUE, CALL_WITH_APP_REGISTERED_FOR_CISCOTEL, TRUE
```

fn.send webex teams message

Given a user's e-mail address, This function sends a Webex Teams message to a single recipient (person). The function uses a markdown template (configured in VOSS) for the message body. This is a Jinja template and supports pwf variables. It optionally attaches a specified file.

```
{{ fn.send_webex_teams_message username@company.com,
   pwf.wt_message_template,
   pwf.csv_file_path }}
```

fn.send_webex_teams_message_email_group

This function sends a Webex Teams message to multiple recipients defined in an email group i.e. data/EmailGroup Uses a markdown template (configured in VOSS) for the message body. This is a Jinja template and supports pwf variables. Optionally attaches a specified file

```
{{ fn.send_webex_teams_message_email_group pwf.email_group,
    pwf.wt_message_template,
    pwf.csv_file_path }}
```

fn.get_webex_teams_device_activation_code

Get an activation code for a Webex Teams device using the Place name as input. This is done by invoking the model operation directly.

```
{{ fn.get_webex_teams_device_activation_code Boardroom }}
```

9.3.14. Subscriber Functions

 fn.process_subscriber_line_data: Used in workflows - a single parameter called input is the workflow input context, containing line data. The function returns line patterns and partitions found in any of Phone, DeviceProfile, RemoteDestinationProfile.

Examples:

Example	Output
{{ fn.process_subscriber_line_data input }}	<pre>[{ "pattern": "10003", "routePartitionName": "Site-23m-Customer 1 Site A" },{ "pattern": "10005", "routePartitionName": "Site-23m-Customer 1 Site A" }]</pre>

9.3.15. Zero, Unset, Boolean, Drop, Null and Exists Functions

Function	Description	Example	Output or Result
fn.zero	Return a zero value.		
		{{fn.zero}}	0
fn.unset	Return an empty string.		
		{{fn.unset}}	11
fn.true	Return a boolean True.		
		{{fn.true}}	true
fn.false	Return a boolean False.		
		{{fn.false}}	false

Given input context:

```
1. {"input": {"field1": {"key1": "value1"}}}
2. {"input": {"field1": None}}
```

```
3. {"input": {"field1": ""}}
```

Function	Description	Example	Input and Result
fn.is_none_or_empty	Return a boolean if the argument is None or an empty string	{{fn.is_none_or_ →empty input.field1}}	input 1. false input 2. true input 3. true

Given input context:

```
{
  "input": {
    "test": null
  }
}
```

Function	Description	Example	Output or Result
fn.null	Returns Null. Useful in comparison tests.	<pre>((input.test == fn.null))</pre>	true

Function	Description	Example	Output or Result
fn.drop	Removes the attribute from CFT	{'name': '{{fn.drop}}'}	Attribute as in existing data
fn.force_null	Attribute has Null value	{'name': '{{fn.force_null}} ''}	{'name': None}

Useful in Configuration Templates (CFT):

Function fn.drop in a CFT will drop a value from the input data when it is processed through a CFT. Input data without the dropped field is then overlaid onto the existing model data by the workflow code. The final payload data for the value will thus *remain the same* as in the existing model data.

Example of fn.drop in an if-then-else test from a CFT of a workflow:

```
"ldapDirectoryName": "(( input.cucm_user_ldapDirectoryName != '' ))
      <{{ input.cucm_user_ldapDirectoryName }}>
      <{{ fn.drop }}"</pre>
```

Function	Description	Example	Output or Result
fn.drop_from_payload	Removes the attribute from payload	{'name': '{{fn.drop_from_	Attribute "blank"

Useful in Configuration Templates (CFT):

Function *fn.drop_from_payload* forces a field to not be present in the final payload data. Used in a CFT, it will drop a value from the existing model data *after* the input data is overlaid onto the existing model data. The value is then not present, i.e. "blanked".

Example of fn.drop_from_payload in a CFT so that attributes are blanked:

```
"meta": {},
"resources": [
  {
    "data": {
      "name": "ConvertCUCUserCFT",
      "target_model_type": "device/cuc/User",
      "template": {
        "LdapType": "0",
        "LdapCcmUserId": "{{ fn.drop_from_payload }}",
        "LdapCcmPkid": "{{ fn.drop_from_payload }}"
      }
    },
    "meta": {
      "model_type": "data/ConfigurationTemplate",
      "system_resource": true,
      "tags": [
        "convertusertype"
  }
]
```

Given input context:

```
1. {"input": {"field1": {"key1": "value1"}}}
2. {"input": {"field1": {"key1": null}}}
3. {"input": {"field1": ""}}
```

Function	Description	Example	Input and Result
fn.exists	Return a boolean true if the argument is exits and has a non-null value.	{{ fn.exists input.field1. ⇔key1 }}	<pre>input 1. true input 2. false input 3. false</pre>
fn.exists	If the argument does not exist, it is interpreted as a string - which is interpretable, so the function returns true.	{{ fn.exists field.key }}	input 1, 2, 3 true

9.3.16. Time Functions

• *fn.now*: Return the date and time at this moment. An optional format parameter is available. Example:

Example	Output
{{fn.now}}	2013-04-18 10:50:52.105130
{{fn.now "%Y%m%d"}} macro.DAY="%A %m/%d/%Y"	20140327
{{fn.now macro.DAY}}	"Thursday 03/27/2014"

Supported date and time formats:

%a	abbreviated weekday name according to the current locale
%A	full weekday name according to the current locale
%b	abbreviated month name according to the current locale
%B	full month name according to the current locale
%с	preferred date and time representation for the current locale
%C	century number (the year divided by 100 and truncated to an integer, range 00 to 99)
%d	day of the month as a decimal number (range 01 to 31)
%D	same as m/d/y
%e	day of the month as a decimal number, a single digit is preceded by a space (range '1' to '31')

continues on next page

Table 1 – continued from previous page

	· · · · · ·
%g	like G, but without the century
%G	The 4-digit year corresponding to the ISO week number
%h	same as b
%H	hour as a decimal number using a 24-hour clock (range 00 to 23)
%l	hour as a decimal number using a 12-hour clock (range 01 to 12)
%j	day of the year as a decimal number (range 001 to 366)
%m	month as a decimal number (range 01 to 12)
%M	minute as a decimal number
%n	newline character
%p	either 'AM' or 'PM' according to the given time value, or the corresponding strings for the current locale
%P	like p, but lower case
%r	time in a.m. and p.m. notation equal to I:M:S p
%R	time in 24 hour notation equal to H:M
%S	second as a decimal number
%t	tab character
%T	current time, equal to H:M:S
%u	weekday as a decimal number [1,7], with 1 representing Monday
%U	week number of the current year as a decimal number, starting with the first Sunday as the first day of the first week
%V	The ISO 8601:1988 week number of the current year as a decimal number, range 01 to 53, where week 1 is the first week that has at least 4 days in the current year, and with Monday as the first day of the week.
%w	day of the week as a decimal, Sunday being 0
%W	week number of the current year as a decimal number, starting with the first Monday as the first day of the first week
%x	preferred date representation for the current locale without the time
%X	preferred time representation for the current locale without the date
%y	year as a decimal number without a century (range 00 to 99)
%Y	year as a decimal number including the century
%z	numerical time zone representation
%Z	time zone name or abbreviation
%%	a literal '%' character

• fn.now_in_tz:

Optional parameters:

- Timezone, entered as listed in *Timezones*.
- time format parameter the time formatting is as with the Supported date and time formats table at *fn.now*.

Without parameters: output is the same as fn.now.

Example:

Example	Output
If current time is 2020-07-01 08:05:07.454918, then	
{{ fn.now_in_tz Australia/Melbourne,%Y-%m-%d →%H:%M:%S }}	2020-07-01 18:08:21
{{ fn.now_in_tz US/Hawaii }}	2020-06-30 22:09:01.935328- →10:00
{{ fn.now_in_tz Etc/GMT }}	2020-07-01 08:09:28. →717503+00:00
{{ fn.now_in_tz }}	2020-07-01 08:09:52.413320

• fn.seconds_to_text: Given an integer seconds value, convert to days, hours, minutes, seconds

Examples	Output
{{ fn.seconds_to_text 345435 }}	3 days, 23 hours, 57 minutes, 15 seconds
{{ fn.seconds_to_text 8000 }}	2 hours, 13 minutes, 20 seconds
{{ fn.seconds_to_text 35 }}	35 seconds

- fn.add_x_days_to_startdate: Given three arguments,
 - a. integer number of days (positive or negative value)
 - b. start date
 - c. date-time format specification

return a date in the past or future.

The arguments can be named macros.

Examples	Output
{{ fn.add_x_days_to_startdate 10,	2019:10:11:02:09
macro.global_setting_cooling_ duration = 10 macro.TODAY_YYYY_MM_DD = '2019-10-01 macro.DateTimeFormatter_YYYY_MM_DD = '%Y:%m:%d:%I:%M'	2019:10:11:02:09
<pre>{{ fn.add_x_days_to_startdate macro.global_setting_cooling_</pre>	

- fn.compare_timestamps: Given two timestamp arguments ts1 and ts2 and also 2 timestamp formats tf1 and tf2, return a value:
 - -1 if ts1 > ts2
 - 0 if ts1 equals ts2
 - -1 if ts1 < ts2

Note: The comma-separated list of parameters should not have spaces between them.

Examples	Output
{{ fn.compare_timestamps 2019-10-01, 2020-10-01, %Y-%m-%d, %Y-%m-%d }}	-1
Comparison of all values in format	
{{ fn.compare_timestamps 2020-02-13T20:45:01, 2020-02-13T20:45:02, %Y-%m-%dT%H:%M:%S, %Y-%m-%dT%H:%M:%S }}	-1
No comparison of omitted values in format	
<pre>{{ fn.compare_timestamps 2020-02-13T20:45:01, 2020-02-13T20:45:02, %Y-%m-%d, %Y-%m-%d }}</pre>	0
{{ fn.compare_timestamps pwf.timestamp_now, pwf.timestamp_expiry, %Y-%m-%d, %Y-%m-%d }}	1

Timezones

Valid timezones list is ['Africa/Abidian', 'Africa/Accra', 'Africa/Addis Ababa', 'Africa/Algiers', 'Africa/Asmara', 'Africa/Asmera', 'Africa/Bamako', 'Africa/Bangui', 'Africa/Banjul', 'Africa/Bissau', 'Africa/Blantyre', 'Africa/Brazzaville', 'Africa/Bujumbura', 'Africa/Cairo', 'Africa/Casablanca', 'Africa/Ceuta', 'Africa/Conakry', 'Africa/Dakar', 'Africa/Dar es Salaam', 'Africa/Djibouti', 'Africa/Douala', 'Africa/El Aaiun', 'Africa/Freetown', 'Africa/Gaborone', 'Africa/Harare', 'Africa/Johannesburg', 'Africa/Juba', 'Africa/Kampala', 'Africa/Khartoum', 'Africa/Kinshasa', 'Africa/Lagos', 'Africa/Libreville', 'Africa/Lome', 'Africa/Kigali'. 'Africa/Luanda'. 'Africa/Lubumbashi', 'Africa/Lusaka', 'Africa/Malabo', 'Africa/Maputo', 'Africa/Maseru', 'Africa/Mbabane', 'Africa/Mogadishu', 'Africa/Monrovia', 'Africa/Nairobi', 'Africa/Ndjamena', 'Africa/Niamey', 'Africa/Nouakchott', 'Africa/Porto-Novo', 'Africa/Sao Tome', 'Africa/Timbuktu', 'Africa/Ouagadougou', 'Africa/Tripoli'. 'Africa/Tunis', 'Africa/Windhoek', 'America/Adak', 'America/Anchorage', 'America/Anguilla', 'America/Antigua', 'America/Araguaina', 'America/Argentina/Buenos_Aires', 'America/Argentina/Catamarca', 'America/Argentina/ComodRivadavia', 'America/Argentina/Cordoba', 'America/Argentina/Jujuy', 'America/Argentina/La Rioja', 'America/Argentina/Mendoza', 'America/Argentina/Rio Gallegos'. 'America/Argentina/Salta'. 'America/Argentina/San Juan'. 'America/Argentina/San Luis'. 'America/Argentina/Tucuman', 'America/Argentina/Ushuaia', 'America/Aruba', 'America/Asuncion', 'America/Atikokan'. 'America/Atka'. 'America/Bahia'. 'America/Bahia Banderas'. 'America/Barbados'. 'America/Belem', 'America/Belize', 'America/Blanc-Sablon', 'America/Boa_Vista', 'America/Bogota', 'America/Boise', 'America/Buenos Aires', 'America/Cambridge Bay', 'America/Campo Grande', 'America/Campo Grande', 'America/Cambridge Bay', 'America/Cambridge Bay', 'America/Cambridge Bay', 'America/Cambridge Bay', 'America/Cambridge Bay', 'America/Campo Grande', 'America/Cambridge Bay', 'America/Campo Grande', 'America/Cambridge Bay', 'America/Cambridge Bay', 'America/Campo Grande', 'America/Cambridge Bay', 'America/Cambridge ica/Cancun', 'America/Caracas', 'America/Catamarca', 'America/Cayenne', 'America/Cayman', 'America/Chicago', 'America/Chihuahua', 'America/Coral Harbour', 'America/Cordoba', 'America/Costa Rica', 'America/Creston', 'America/Cuiaba', 'America/Curacao', 'America/Danmarkshavn', 'America/Dawson', 'America/Dawson_Creek', 'America/Denver', 'America/Detroit', 'America/Dominica', 'America/Edmonton', 'America/Eirunepe', 'America/El Salvador', 'America/Ensenada', 'America/Fort Wayne', 'America/Fortaleza', 'America/Godthab'. 'America/Goose Bay', 'America/Grand Turk', 'America/Glace Bay'.

ica/Grenada', 'America/Guadeloupe', 'America/Guatemala', 'America/Guayaguil', 'America/Guyana', 'America/Havana', 'America/Hermosillo', 'America/Indiana/Indianapolis', 'America/Halifax', ica/Indiana/Knox', 'America/Indiana/Marengo', 'America/Indiana/Petersburg', 'America/Indiana/Tell City', 'America/Indiana/Vevay', 'America/Indiana/Vincennes', 'America/Indiana/Winamac', 'America/Indianapolis', 'America/Inuvik', 'America/Igaluit', 'America/Jamaica', 'America/Jujuy', 'America/Juneau', 'America/Kentucky/Louisville', 'America/Kentucky/Monticello', 'America/Knox_IN', 'America/Kralendijk', 'America/Kentucky/Louisville', 'America/Kentucky/Louisvil ica/La Paz'. 'America/Lima'. 'America/Los Angeles'. 'America/Louisville'. 'America/Lower Princes'. 'America/Maceio', 'America/Managua', 'America/Manaus', 'America/Marigot', 'America/Martinique', 'America/Matamoros', 'America/Mazatlan', 'America/Mendoza', 'America/Menominee', 'America/Merida', 'America/Metlakatla', 'America/Mexico_City', 'America/Miquelon', 'America/Moncton', 'America/Monterrey', 'America/Montevideo', 'America/Montreal', 'America/Montserrat', 'America/Nassau', 'America/New York', 'America/Nipigon', 'America/Nome', 'America/Noronha', 'America/North Dakota/Beulah', ica/North_Dakota/Center', 'America/North_Dakota/New_Salem', 'America/Ojinaga', 'America/Panama', 'America/Pangnirtung', 'America/Paramaribo', 'America/Phoenix', 'America/Port-au-Prince', 'America/Port of Spain'. 'America/Porto Acre', 'America/Porto Velho', 'America/Puerto Rico', ica/Rainy River'. 'America/Rankin Inlet', 'America/Recife', 'America/Regina', 'America/Resolute', 'America/Rio Branco', 'America/Rosario', 'America/Santa Isabel', 'America/Santarem', 'America/Santiago', 'America/Santo Domingo', 'America/Sao Paulo', 'America/Scoresbysund', 'America/Shiprock', 'America/Sitka', 'America/St Barthelemy', 'America/St Johns', 'America/St Kitts', 'America/St Lucia', 'America/ ica/St_Thomas', 'America/St_Vincent', 'America/Swift_Current', 'America/Tegucigalpa', 'America/Thule', 'America/Thunder_Bay', 'America/Tijuana', 'America/Toronto', 'America/Tortola', 'America/Vancouver', 'America/Virgin', 'America/Whitehorse', 'America/Winnipeg', 'America/Yakutat', 'America/Yellowknife', 'Antarctica/Casey', 'Antarctica/Davis', 'Antarctica/DumontDUrville', 'Antarctica/Macquarie', 'Antarctica/Mawson', 'Antarctica/McMurdo', 'Antarctica/Palmer', 'Antarctica/Rothera', 'Antarctica/South Pole', 'Antarctica/Syowa', 'Antarctica/Vostok', 'Arctic/Longyearbyen', 'Asia/Aden', 'Asia/Almaty', 'Asia/Amman', 'Asia/Anadyr', 'Asia/Agtau', 'Asia/Agtobe', 'Asia/Ashgabat', 'Asia/Ashkhabad', 'Asia/Baghdad', 'Asia/Bahrain', 'Asia/Baku', 'Asia/Bangkok', 'Asia/Beirut', 'Asia/Bishkek', 'Asia/Brunei', 'Asia/Calcutta', 'Asia/Choibalsan', 'Asia/Chongqing', 'Asia/Chungking', 'Asia/Colombo', 'Asia/Dacca', 'Asia/Damascus', 'Asia/Dhaka', 'Asia/Dili', 'Asia/Dubai', 'Asia/Dushanbe', 'Asia/Gaza', 'Asia/Harbin', 'Asia/Hebron', 'Asia/Ho Chi Minh', 'Asia/Hong Kong', 'Asia/Hovd', 'Asia/Irkutsk', 'Asia/Istanbul', 'Asia/Jakarta', 'Asia/Jayapura', 'Asia/Jerusalem', 'Asia/Kabul', 'Asia/Kamchatka', 'Asia/Karachi', 'Asia/Kashgar', 'Asia/Kathmandu', 'Asia/Katmandu', 'Asia/Khandyga', 'Asia/Kolkata', 'Asia/Krasnoyarsk', 'Asia/Kuala_Lumpur', 'Asia/Kuching', 'Asia/Kuwait', 'Asia/Macao', 'Asia/Macau', 'Asia/Magadan', 'Asia/Makassar', 'Asia/Manila', 'Asia/Muscat', 'Asia/Nicosia', 'Asia/Novokuznetsk', 'Asia/Novosibirsk', 'Asia/Omsk', 'Asia/Oral', 'Asia/Phnom Penh', 'Asia/Pontianak', 'Asia/Pyongyang', 'Asia/Qatar', 'Asia/Qyzylorda', 'Asia/Rangoon', 'Asia/Riyadh', 'Asia/Saigon', 'Asia/Sakhalin', 'Asia/Samarkand', 'Asia/Seoul', 'Asia/Shanghai', 'Asia/Singapore', 'Asia/Taipei', 'Asia/Tashkent', 'Asia/Tbilisi', 'Asia/Tehran', 'Asia/Tel Aviv', 'Asia/Thimbu', 'Asia/Thimphu', 'Asia/Tokyo', 'Asia/Ujung Pandang', 'Asia/Ulaanbaatar', 'Asia/Ulan_Bator', 'Asia/Urumqi', 'Asia/Ust-Nera', 'Asia/Vientiane', 'Asia/Vladivostok', 'Asia/Yakutsk', 'Asia/Yekaterinburg', 'Asia/Yerevan', 'Atlantic/Azores', 'Atlantic/Bermuda', 'Atlantic/Canary', 'Atlantic/Cape_Verde', 'Atlantic/Faeroe', 'Atlantic/Faroe', 'Atlantic/Jan_Mayen', 'Atlantic/Madeira', 'Atlantic/Reykjavik', 'Atlantic/South Georgia', 'Atlantic/St Helena', 'Atlantic/Stanley', 'Australia/ACT', 'Australia/Adelaide', 'Australia/Brisbane', 'Australia/Broken Hill', 'Australia/Canberra', 'Australia/Currie', 'Australia/Eucla', 'Australia/Hobart', 'Australia/LHI', 'Australia/Lindeman', 'Australia/Darwin'. 'Australia/Melbourne', 'Australia/NSW', 'Australia/North', 'Australia/Perth', 'Australia/North', 'Australia/ tralia/Lord Howe', tralia/Queensland'. 'Australia/South', 'Australia/Sydney', 'Australia/Tasmania', 'Australia/West', 'Australia/Yancowinna', 'Brazil/Acre', 'Brazil/DeNoronha', 'Brazil/East', 'Brazil/West', 'CET', 'CST6CDT', 'Canada/Atlantic', 'Canada/Central', 'Canada/East-Saskatchewan', 'Canada/Eastern', 'Canada/Mountain', 'Canada/Newfoundland', 'Canada/Pacific', 'Canada/Saskatchewan', 'Canada/Yukon', 'Chile/Continental', 'Chile/EasterIsland', 'Cuba', 'EET', 'EST', 'EST5EDT', 'Egypt', 'Eire', 'Etc/GMT', 'Etc/GMT+0', 'Etc/GMT+1', 'Etc/GMT+10', 'Etc/GMT+11', 'Etc/GMT+12', 'Etc/GMT+2', 'Etc/GMT+3', 'Etc/GMT+4', 'Etc/GMT+5', 'Etc/GMT+6', 'Etc/GMT+7', 'Etc/GMT+8', 'Etc/GMT+9', 'Etc/GMT-0', 'Etc/GMT-1', 'Etc/GMT-10', 'Etc/GMT-11', 'Etc/GMT-12', 'Etc/GMT-13', 'Etc/GMT-14', 'Etc/GMT-2', 'Etc/GMT-3', 'Etc/GMT-4', 'Etc/GMT-5', 'Etc/GMT-6', 'Etc/GMT-7', 'Etc/GMT-8', 'Etc/GMT-9', 'Etc/GMT0', 'Etc/Greenwich', 'Etc/UCT', 'Etc/UTC', 'Etc/Universal', 'Etc/Zulu', 'Europe/Amsterdam', 'Europe/Andorra', 'Europe/Athens', 'Europe/Belfast', 'Europe/Belgrade', 'Europe/Berlin', 'Europe/Bratislava', 'Europe/Brussels', 'Europe/Bucharest', 'Europe/Budapest', 'Europe/Busingen', 'Europe/Chisinau', 'Europe/Copenhagen', 'Europe/Dublin', 'Europe/Gibraltar', 'Europe/Guernsey', 'Europe/Helsinki', 'Europe/Isle of Man', 'Europe/Istanbul', 'Europe/Jersey', 'Europe/Kaliningrad', 'Europe/Kiev', 'Europe/Lisbon', 'Europe/Ljubljana', 'Europe/London', 'Europe/Luxembourg', 'Europe/Madrid', 'Europe/Malta', 'Europe/Mariehamn', 'Europe/Minsk', 'Europe/Monaco', 'Europe/Moscow', 'Europe/Nicosia', 'Europe/Oslo', 'Europe/Paris', 'Europe/Podgorica', 'Europe/Prague', 'Europe/Riga', 'Europe/Rome', 'Europe/Samara', 'Europe/San Marino', 'Europe/Saraievo', 'Europe/Simferopol', 'Europe/Skopje', 'Europe/Sofia', 'Europe/Stockholm', 'Europe/Tallinn', 'Europe/Tirane', 'Europe/Tiraspol', 'Europe/Uzhgorod', 'Europe/Vaduz', 'Europe/Vatican', 'Europe/Vienna', 'Europe/Vilnius', 'Europe/Volgograd', 'Europe/Warsaw', 'Europe/Zagreb', 'Europe/Zaporozhye', 'Europe/Zurich', 'GB', 'GB-Eire', 'GMT', 'GMT+0', 'GMT-0', 'GMT0', 'Greenwich', 'HST', 'Hongkong', 'Iceland', 'Indian/Antananarivo', 'Indian/Chagos', 'Indian/Christmas', 'Indian/Cocos', 'Indian/Comoro', 'Indian/Kerguelen', 'Indian/Mahe', 'Indian/Maldives', 'Indian/Mauritius', 'Indian/Mayotte', 'Indian/Reunion', 'Iran', 'Israel', 'Jamaica', 'Japan', 'Kwajalein', 'Libya', 'MET', 'MST', 'MST7MDT', 'Mexico/BajaNorte', 'Mexico/BajaSur', 'Mexico/General', 'NZ', 'NZ-CHAT', 'Navajo', 'PRC', 'PST8PDT', 'Pacific/Apia', 'Pacific/Auckland', 'Pacific/Chatham', 'Pacific/Chuuk', 'Pacific/Easter', 'Pacific/Efate', 'Pacific/Enderbury', 'Pacific/Fakaofo', 'Pacific/Fiji', 'Pacific/Funafuti', 'Pacific/Galapagos', 'Pacific/Gambier', 'Pacific/Guadalcanal', 'Pacific/Guam', 'Pacific/Honolulu', 'Pacific/Johnston', 'Pacific/Kiritimati', 'Pacific/Kosrae', 'Pacific/Kwajalein', 'Pacific/Majuro', 'Pacific/Marquesas', 'Pacific/Midway', 'Pacific/Nauru', 'Pacific/Niue', 'Pacific/Norfolk', 'Pacific/Noumea', 'Pacific/Pago Pago', 'Pacific/Palau', 'Pacific/Pitcairn', 'Pacific/Pohnpei', 'Pacific/Ponape', 'Pacific/Port Moresby', 'Pacific/Rarotonga', 'Pacific/Saipan', 'Pacific/Samoa', 'Pacific/Tahiti', 'Pacific/Tarawa', 'Pacific/Tongatapu', 'Pacific/Truk', 'Pacific/Wake', 'Pacific/Wallis', 'Pacific/Yap', 'Poland', 'Portugal', 'ROC', 'ROK', 'Singapore', 'Turkey', 'UCT', 'US/Alaska', 'US/Aleutian', 'US/Arizona', 'US/Central', 'US/East-Indiana', 'US/Eastern', 'US/Hawaii', 'US/Indiana-Starke', 'US/Michigan', 'US/Mountain', 'US/Pacific', 'US/Pacific-New', 'US/Samoa', 'UTC', 'Universal', 'W-SU', 'WET', 'Zulu']

9.3.17. Hierarchy Functions

- fn.hierarchy: Return the UUID of the current node.
- fn.hierarchy_parent: Return the UUID of the parent.
- fn.hierarchy_path: Return the current node hierarchy as a list of UUIDs.
- fn.hierarchy_parent_path: Return the current node parent hierarchy as a list of UUIDs.
- fn.hierarchy friendly path: Return the current node hierarchy as a dot-separated hierarchy string.
- fn.hierarchy_friendly_parent_path: Return the current node parent hierarchy as a dot-separated hierarchy string.
- fn.friendly_path_choices: Return a sorted list of friendly hierarchy paths. Used with a parameter:
 - down: all hierarchies paths below, including current hierarchy path
 - below: all hierarchies below current hierarchy path, excluding current hierarchy path
 - local: current hierarchy path
- fn.is site: Return true or false if run at site context hierarchy or not.

Examples:

Example	Output
{{fn.hierarchy}}	'52162d552afa433946245bcb'
{{fn.hierarchy_parent}}	'52162d522afa433941245ba0'
{{fn.hierarchy_path}}	['1c0efeg2c0deab10da595101', '52162d4c2afa433940245ba3', '52162d4e2afa43393b245ba2', '52162d522afa433941245ba0', '52162d552afa433946245bcb']
{{fn.hierarchy_parent_path}}	['1c0efeg2c0deab10da595101', '52162d4c2afa433940245ba3', '52162d4e2afa43393b245ba2', '52162d522afa433941245ba0']
{{fn.hierarchy_friendly_path}}	'sys.GenCorp.SuperCom.ABCGroup. Branch1'
{{fn.hierarchy_friendly_parent_path}}	'sys.GenCorp.SuperCom.ABCGroup'
<pre>Hierarchy = sys.hcs.CS-P.CS-NB.AAAGlobal</pre>	r
{# fn.friendly_path_choices ,down #}	"sys.hcs.CS-P.CS-NB.AAAGlobal", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC001", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC002", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC003", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC004", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC005", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOC005", "sys.hcs.CS-P.CS-NB.AAAGlobal. →LOCALIZE001"]
<pre>Hierarchy = sys.hcs.CS-P.CS-NB.AAAGlobal (cust)</pre>	false
{{ fn.is_site }}	

9.3.18. User Details Request Functions

Function	Description	Example
fn.request_user_name	Return the logged in username.	
		{{fn.request_user_name}}
fn.request_user_role	Return the logged in user role.	
		{{fn.request_user_role}}
fn.request_user_email	Return the logged in user email address.	{{fn.request_user_email}}
fn.request_user_pkid	Return the logged in user pkid.	{{fn.request_user_pkid}}

9.3.19. Number Management Functions

CUSTOMER_INI_ENABLED

The fn.get_lines macro function uses the value of a CUSTOMER_INI_ENABLED macro at the relevant hierarchy:

- If ((True)), then apply the function to the Internal Number Inventory (INI) at the hierarchy: data. InternalNumberInventory.internal_number.
- If ((False)), then apply the function to device.cucm.Line.pattern.

The macro function will check the CUSTOMER_INI_ENABLED macro first. This macro should exist at the required hierarchy level and have a value of ((True)) or ((False)).

Function

Function name: fn.get_lines.

Example where CUSTOMER_INI_ENABLED macro is ((True)):

Example	Output
{{fn.get_lines}}	[{"value": "1000",
_	"title": "1000 (Used) \\+27826543001",
	{"value": "2000",
	"title": "2000"},
	{"value": "3000",
	"title": "3000 (Used-Utility)"},
	{"value": "4000",
	"title": "4000 (Cooling) \\+27826543004
	→(release date: 2021-09-25)"},
	{"value": "5000",
	"title": "5000 (Reserved)"}]
	, , , , , ,

Parameters

The parameter names and values are listed below.

Note: More than one parameter can be used. These should then be comma-separated, for example: { fn.get_lines status:Used, direction:parent}}.

• status: the status of the line.

Parameter values:

- **-** All
- Available
- Used
- Available_or_Used
- Used-Utility
- Used_or_Used-Utility
- Reserved
- Cooling

For details, refer to the Number Status and Usage topic in the Core Feature Guide.

Usage example: {{fn.get_lines status:Available}}

Example	Output
{{fn.get_lines status:Available}}	[{"value": "2000", "title": "2000"}]

• direction: the line search direction in the hierarchy.

Note: The default search direction is up, i.e. without the parameter is equal to direction: up.

Parameter values:

- up Upwards. Include current hierarchy. This is the default if the parameter is not used.
- down Downwards. Include current hierarchy.
- local: On this level only. Include current hierarchy.
- parent Parent only. Exclude current hierarchy, in other words, search the parent as local.
- below Downwards. Exclude current hierarchy.
- above Upwards. Exclude current hierarchy.

Usage example: {{fn.get_lines direction:parent}}

Example	Output
{{fn.get_lines direction:parent}}	[{"value": "1000", "title": "1000 (Used) \\+27826543001"}, {"value": "3000", "title": "3000 (Used-Utility)"}]

• partition: the line search is for device.cucm.Line.pattern in the specified partition only, i.e. the specified routePartitionName.

Parameter value: a partition name, for example Site-REL103-Customer.

Example	Output
{{fn.get_lines partition:Site-REL103-	[{"value": "2000",
→Customer}}	"title": "2000"}

• e164: the line search is for the E164 number.

Parameter value: an E164 number, for example \+27826543001.

Example	Output
{{fn.get_lines e164:"\+27826543001"}} ↔	[{"value": "1000", "title": "1000 (Used) \\+27826543001"}

• scalar_list_only:true: only display the value in the title, value pair of the result list.

Parameter value: only one value: true. Without the parameter, the default display is the title, value pair.

Example	Output
{{fn.get_lines scalar_list_only:true}	[
\hookrightarrow }	"1000",
	"2000",
	"3000",
	"4000",
	"5000"
]

Parameter Types and Permutations

Parameters are of the following types:

- Applies to INI: status, e164
- Applies to cucm/Line: partition
- Other: scalar_list, direction

The types of parameters will determine the types of lines returned:

- Internal Number Inventory or
- device.cucm.Line.pattern

in accordance with whether CUSTOMER_INI_ENABLED is ((True)) or ((False)).

The table below shows the result of parameters and combinations used in these cases.

Note: The default (if not specified) direction is up.

Parameter Combination	INI en- abled	Result
partition[scalar_list, direction]	Y	Return cucm.Line in partition
partition[scalar_list, direction]	N	Return cucm.Line in partition
status, partition	Y	Return INI by status upwards
status, partition	N	Return cucm.Line in partition
status	Y	Return INI by status upwards
status	N	Return cucm.Line upwards
partition	Υ	Return cucm.Line in partition
partition	N	Return cucm.Line in partition

Get DN Number from E164 Range

fn.get_dn_number: Return the matching Directory Number (DN) in a range given a E164 number as input. The E164 ranges are of 1, 10, 100 and 1000.

Two models are queried. If no results are found in data/HcsDpDNE164AssociateDAT then the ranges in data/HcsDpDNMultiE164AssociateDAT are queried.

Examples:

Example	Output
hierarchy: sys.hcs.CS.Global.LOC002	82041000
{{ fn.get_dn_number	

9.3.20. Phone Functions

Function names:

fn.get_phone_status

Given as input parameters:

- a phone PKID
- followed by a comma and then exactly one RIS API field name.

The fields below are for example used in the VOSS-4-UC Admin Portal list view of Phones:

- * status
- * ip_address
- * cm_node

To see a full list of available fields, refer to the Cisco RIS API documentation.

Returns:

A string with the results according to the selected field name

Examples:

Example	Output
{{fn.get_phone_status 5ca2b90bce894e0014d488fb, Status}}	"Registered"

· fn.get phone statuses

Given as input parameters:

- a semicolon separated list of phone PKIDs
- optionally followed by a comma and then a semicolon separated list of RIS API field names.

The fields below are for example used in the VOSS-4-UC Admin Portal list view of Phones:

- * status
- * ip_address
- * cm_node

To see a full list of available fields, run the macro function without RIS API field names or refer to the Cisco RIS API documentation.

Returns:

A list of phone status results with details:

- containing either all fields if no optional field name list was provided, or
- if an optional field name list was provided, results according to the selected field names.

Note: This function will query the Unified CM for the requested PKIDs and return the phone registration status of these.

Examples:

Example	Output
{{fn.get_phone_statuses	[{ "Status": "Registered", "ip_address": "172.29.90.80" }, { "Status": "Registered", "ip_address": "172.29.90.11" }]

fn.get_hierarchy_phone_statuses

A function to retrieve phone statuses as JSON objects with the phone name as the key. including those not returned by the Call Manager API

Given as input parameters:

- status - a phone status:

The status parameter value is case insensitive, for example Unregistered will also find UnRegistered.

- * Registered
- * Unregistered
- * PartiallyRegistered
- * Rejected
- * Any
- * Unknown
- * None will return only phones not returned by the Unified CM API; the only data will be hierarchy, phone name and status (None).
- optionally followed by value of cucm (host or pkid)

Note:

- If the function is run at a hierarchy above customer level, the parameter is mandatory.
- * The function will yield an error if more than one cucm host has the same name. Use the pkid as value in this case.
- optionally followed by value of device_name (phone name prefix: "startswith" match, e.g. SEP, BOT...)
- optionally followed by value of ip_address (IP address: partial "startswith" match, e.g. "10.10." is valid)
- optionally followed by value of dir_number (directory number: "startswith" match, does not have to be the whole number)

semicolon separated list of RIS API field names.

The fields below are for example used in the VOSS-4-UC Admin Portal list view of Phones:

- * status
- * ip_address
- * cm node

To see a full list of available fields, run the macro function without RIS API field names or refer to the Cisco RIS API documentation.

Returns:

A list of phone status results with details:

- containing either all fields if no optional field name list was provided, or
- if an optional field name list was provided, results according to the selected field names.

Examples:

Example	Output (truncated)
{{fn.get_hierarchy_phone_statuses Registered}}	{ "CTICTIREM": { "hierarchy": "sys.hcs.CS-P.CS-NB. →AAAGlobal", "cm_node": "cucm", "ip_address": "172.29.90.80", "status": "Registered with cucm", "Name": "CTICTIREM", "DirNumber": "82025608- →Registered", "DeviceClass": "Phone", []

· fn.save hierarchy phone statuses

A function to retrieve phone statuses as a Comma Separated Value (CSV) file that is stored in the database as an instance of $\mathtt{data/File}$ and accessible from the **File Management** menu on the GUI. The CSV file can for example be exported (as JSON with .zip extension, containing JSON and CSV files) and managed in a spreadsheet.

The status parameter value is case insensitive, for example Unregistered will also find UnRegistered.

The CSV filename format with a parameter value for <fname_prefix> is:

- <fname_prefix>_<hierarchy_name>_<status>_<timestamp>_<number of entries>.csv otherwise, the CSV filename format is:
 - <hierarchy_name>_<status>_<timestamp>_<number of entries>.csv

The <timestamp> format is: %Y%m%d_%H%M%S

Input parameters as with *fn.get_hierarchy_phone_statuses*, and:

- optionally followed by a value of fname_prefix (CSV filename prefix)

Examples:

Example	Output (also refer to data/File instance)
{{fn.save_hierarchy_phone_statuses Registered}}	{ "url": "/api/data/File/ →5bf43f83affa931c2505f6a6/", "description": "AAAGlobal_ →Registered_20201014)161506_3" }

9.3.21. Localization Functions

- fn.localize: Return a value that is localized, in other words it will be translated if a translation exists. It is used with a macro call that returns a value from a data store.
- fn.list_installed_languages: List the installed languages on the system. This includes languages in the Admin Portal and selfservice GUI.
- fn.list_installed_languages_admin: List the installed languages in the Admin Portal.
- fn.list_installed_languages_selfservice: List the installed languages in the selfservice GUI.
- fn.list_installed_languages_by_role: List the installed languages based on the User Role Interface value.

The User Role Interface value is a parameter of this function:

- admin installed languages in the Admin Portal
- self-service selfservice GUI
- none union of admin and selfservice languages
- fn.localize_choices: Given a parameter containing a list of strings, return title-value pairs of the strings, with the titles marked for localization. The function is used to localize drop-down lists. For example, given a list:

```
[ 'choice1', 'choice2' ]
```

then the function will return

which is then localized upon rendering. For English, this will simply be:

Example	Output
<pre>{{ fn.localize data.LocalizedModelStore. localized_value where_clause }}</pre>	A localized value is returned.
{# fn.list_installed_languages #}	<pre>[{'value': 'en-us', 'title': 'English'}, {'value': 'de-de', 'title':'German'}]</pre>
{ # fn.list_installed_languages_admin #}	[{'value':'en-us', 'title': 'English'}]
{# fn.list_installed_languages_selfservice #}	<pre>[{'value': 'en-us', 'title': 'English'}, {'value': 'de-de', 'title': 'German'}]</pre>
{# fn.list_installed_languages_by_role none #}	<pre>[{'value': 'en-us', 'title': 'English'}, {'value': 'de-de', 'title': 'German'}]</pre>
<pre>{{ fn.localize_choices data.HcsNbnSupportedModelsDAT.operations modelType:data/User }}</pre>	<pre>output before localization: [{'title': _('create'), 'value': 'create'}, {'title': _('delete'), 'value': 'delete'}, {'title': _('update'), 'value': 'update'}]</pre>

9.3.22. Log Functions

- *fn.log*: Given a log level and message, display it in the log. Log levels can be: debug, critical, warn, error or info.
- fn.txn_log: Given a message, display it in the transaction log on the Admin Portal.

 The macro is typically added to a workflow "Set" step for debugging purposes.

Examples:

Example	Output
	<pre>In app.log:</pre>
<pre>{{fn.log info, This is an informational message.}}</pre>	INFO This is an informational message.
{{fn.log debug, Debug message.}}	DEBUG Debug message.
A workflow (1PWF) step Set variable "bar" is a message with the value of "name".	Step 1 - Set workflow context (1PWF):
{{fn.txn_log pwf.name}}	<pre>"set_list": [</pre>

For examples of the macros below, refer to the example for Custom Messages and Details in Provisioning Workflows.

• fn.set_current_transaction_detail(<detail_text>)

To customize the transaction detail of the *current* transaction: top (ancestor) or child transaction. If a transaction fails, this detail will also override the standard detail.

• fn.set_top_level_transaction_detail(<detail_text>)

To customize the transaction detail of the top (ancestor) transaction. If there is no top transaction, it will customize the current transaction detail. If a transaction fails, this detail will also override the standard detail.

• fn.set_current_transaction_message(<message_text>)

To customize the transaction message of the *current* transaction: top or child transaction. If a transaction fails, this message will *not* override the standard error message.

• fn.set_top_level_transaction_message(<message_text>)

To customize the transaction message of the top transaction. If there is no top transaction, it will customize the current transaction message. If a transaction fails, this message will *not* override the standard error message.

9.3.23. Object Functions

- fn.is_object: Return true or false if the parameter is an object or not.
- fn.object_keys: Given an object and additional optional parameter, return the list of keys that match the parameter value, or all the keys if no parameter value is given.

Example object:

```
"input": {
    "object": {
        "boolean_1": true,
        "boolean_2": false,
        "boolean_3": true,
        "string_1": "1",
        "string_1_dup": "1",
        "string_2": "2",
        "integer_1": 1,
        "integer_1_dup": 1,
        "integer_2": 2
```

Examples:

Example	Output
{{ fn.object_keys input.object,true }}	["boolean_1","boolean_3"]
{{fn.object_keys input.object,"1"}}	["string_1","string_1_dup"]
{{fn.object_keys input.object,1}}	["integer_1","integer_1_dup"]
{{fn.object_keys input.object}}	<pre>["boolean_1", "boolean_2", "boolean_3", "string_1", "string_1_dup", "string_2", "integer_1", "integer_1_dup", "integer_2"]</pre>

• fn.object_empty: Returns and empty object

Example:

Example	Output
{{ fn.object_empty }}	{}

- fn.object_update Given an existing object and a key-value pair, updates and returns the given object with the key and value.
 - If the key dows not exist, the pair is added.
 - If the key exists, the value is updated.

Examples:

Example	Output
my_object:	
<pre>{ "existing_key": "some_value" } function call:</pre>	{ "existing_key": "some_value", "key": "1234" }
{{ fn.object_update "key","1234", input.my_object }}	
my_object:	
{ "key": "some_value" } function call:	{ "key": "1234" }
<pre>{{ fn.object_update "key","1234",</pre>	

9.3.24. Conversion Functions

- fn.pkid to bkey: Given a pkid, return the business key.
- fn.bkey to pkid: Given a business key, return the pkid Provide the data type as an argument.
- · fn.from business key format: Convert a field business key string format to a list
- fn.as_int: Given a string, return an integer.
- fn.as_string: Given an integer, return a string.
- fn.as_bool: Given strings "True", "TRUE", "T", "t", "1", return True. Given strings "False", "FALSE", "F", "f", "0", return False.
- fn.as list: Given input, return it as a list. List input is returned as is.
- fn.int_to_hex: Return the hexadecimal value of an integer. Application example: for gateways that use hexadecimal values for port numbers.
- fn.hex_to_int: Return the integer value of a hexadecimal value. Application example: for gateways that use hexadecimal values for port numbers.
- *fn.getMajorMinorVersion*: Given a version in various formats, return a version of the format <major>.<minor>.
- fn.list_to_string: Given a list as input, return the list as a string.

Note the following in the output - refer to the example below:

- strings in the list will be prefixed with a Unicode character u
- the "[" and "]" as well as the commas between list items are included in the converted string
- fn.list_items_to_string: Given a list as input (strings or integers), return each item as a string.
 Only simple lists are supported.

fn.list_items_to_int: Given a list of integers as input, return each item as a string.
 Only simple lists are supported.

Only lists of integers are supported.

Examples:

Example	Output
<pre>macro: USA_pkid = {{data.Countriespkid iso_country_code:USA}} {{fn.pkid_to_bkey macro.USA_pkid}}</pre>	"[u'United States of America', u'USA', u'']"
<pre>macro: a_country_bkey = {{data.Countriesbkey pkid:macro.USA_pkid}} {{fn.bkey_to_pkid macro.a_country_bkey, data/Countries}}</pre>	"52d3eba8893d57373f842acb"
<pre>context data: { "self": {</pre>	["10.110.21.101", "8443", "hcs.CS-P.CS-NB.AAAGlobal"

Example	Output
{{fn.as_int "1"}}	1
{{fn.as_string 12345}}	"12345"
{{fn.as_bool "T"}}	true
{{fn.as_bool "0"}}	false
{#fn.as_list foo bar#} {#fn.as_list 'foo,bar'#} {#fn.as_list ['foo','bar']#}	['foo bar'] ['foo,bar'] ['foo','bar']
{{fn.int_to_hex 255}}	ff
{{fn.hex_to_int ff}}	255

Example	Output
{{ fn.getMajorMinorVersion 10.5(4) }}	10.5
{{ fn.getMajorMinorVersion 11.5(1) SU1 }}	11.5
{{ fn.getMajorMinorVersion 11.5.3 }}	11.5
<pre>{"pwf": { "my_list": [1, null, 2,"test", 3, null] } }</pre>	"[1, None, 2, u'test', 3, None]
<pre>{{ fn.list_to_string pwf.my_list }}</pre>	
<pre>{"pwf": { "my_list": [1, 2, "3", 4] } }</pre>	['1', '2', '3', '4']
<pre>{{ fn.list_items_to_string pwf.my_list }}</pre>	
{"pwf": { "my_list": [1, 2, "3", 4] } }	[1, 2, 3, 4]
{{ fn.list_items_to_int pwf.my_list }}	

9.3.25. HTTP Functions

• fn.request_get: Return in JSON format the response of an HTTP request. The HTTP request must start with http://localhost

Example request:

```
{{ fn.request_get http://localhost/api/data/Countries/properties }}
```

The output can be assigned to a variable so that properties can be referenced.

Example with output snippet:

```
http://localhost/api/data/Countries/properties
```

```
{
    "meta": {
        "query": "/api/data/Countries/properties/?hierarchy=[hierarchy]&format=json"
```

(continues on next page)

Example of instance output with GET request for an instance with [pkid]:

http://localhost/api/data/Countries/54elde60edec65160652e402

```
. . .
 ],
     "business_key": {
         "hierarchy": true,
         "unique": [
             "country_name",
             "iso_country_code"
     "tagged_versions": []
},
"data": {
    "iso_country_code": "MEX",
      "pstn_access_prefix": "9",
      "pkid": "54e1de60edec65160652e403",
      "default_user_locale": "English United States",
      "network_locale": "United States",
      "standard_access_prefix": "0",
      "international_access_prefix": "00",
      "country_name": "Mexico",
      "international_dial_code": "52",
      "emergency_access_prefix": "066",
      "national_trunk_prefix": "01"
    }
```

• fn.perform_http_get: Given a URL parameter and optionally username and password parameters, return in HTTP status code of the HTTP request.

Example request:

```
{{ fn.perform_http_get http://<hostname> }}
```

Example request with additional parameters:

```
{{ fn.perform_http_get http://<hostname> <username> <password>}}
```

Example output:

200

If the HTTP request raises an error (for example: not found, connection, timeout, and so on), this error will be returned.

9.3.26. **File Functions**

• fn.write temporary local_file: Given a filename and text data, write the data to the filename onto the file system temporary directory.

This file can for example be used as an e-mail attachment parameter for the *fn.email html* function. See: Email Functions.

Syntax:

```
{{ fn.write_temporary_local_file mydata.csv,pwf.SomeData }}
```

where:

- the value for example sets pwf.file_path, to be used as a parameter of:

```
{{ fn.email_html pwf.to,pwf.from,pwf.template,pwf.file_path }}
```

- mydata.csv is the example filename
- pwf.SomeData references a string value of SomeData in an example workflow from where the function is called.

Email Functions 9.3.27.

- fn.email html: Given the parameters:
 - to: addressee email address
 - from: sender email address
 - template: email template
 - file path: attachment (optional) See File Functions.

send an email if an SMTP server is set up at the hierarchy from which the function is called.

The function is typically used in provisioning workflows to send an email to a subscriber using the Quick Add Subscriber feature if this has been set up - see: Global Settings.

Syntax:

```
{{ fn.email_html pwf.to,pwf.from,pwf.template,pwf.file_path }}
```

the parameters have been assigned values in the workflow.

Workflow snippet example:

```
"entity": "data/ProvisioningWorkflow",
"entity_type": "model",
"method": "set",
"set_list": [
                                                                      (continues on next page)
```

9.4. Macro Examples and Use

9.4.1. Macro Examples - Simple

Simple macros must always resolve to one value only.

```
{{data.Countries.iso_country_code | country_name:'South Africa'}}
'ZAF'
```

Call to a non-existent macro.

```
{{macro.DoesNotExist}}

{u'code': 6003,
  u'http_code': 400,
  u'message': u'Macro lookup of macro.DoesNotExist failed at hierarchy sys',
  u'transaction': None}
```

First Partition member name in CSS PSTN-CSS-Cape-Town.

```
{{ device.cucm.Css.members.member.0.routePartitionName | name: 'PSTN-CSS-Cape-Town' }}

'PHONES-PT-Cape-Town'
```

First Partition member UUID in CSS PSTN-CSS-Cape-Town.

```
{{ device.cucm.Css.members.member.0.uuid | name: 'PSTN-CSS-Cape-Town' }}

'{7AF255DC-3A05-A1B4-9E5E-95CD48C3C95F}'
```

9.4.2. Macro Examples - List Macro

Syntax for List macros is between {# #}. The results are in a list format: comma separated results and between [] All fields in Countries model.

```
{ # data.Countries.* #}
[{u'cli_on_prefix': u'',
 u'country_name': u'Australia',
 u'data_type_': u'data/Countries',
 u'default_user_locale': u'English United States',
 u'emergency_access_prefix': u'000',
 u'international access prefix': u'011',
 u'international_dial_code': u'61',
 u'iso_country_code': u'AUS',
 u'national_trunk_prefix': u'0',
 u'network_locale': u'United States',
 u'premium_access_prefix': u'8',
 u'pstn_access_prefix': u'9',
 u'service_access_prefix': u'13'},
{u'cli_on_prefix': u'',
 u'country_name': u'Bahrain',
 u'data_type_': u'data/Countries',
 u'default_user_locale': u'English United States',
 u'emergency_access_prefix': u'999',
 u'international_access_prefix': u'00',
 u'international_dial_code': u'973',
 u'iso_country_code': u'BHR',
 u'national_trunk_prefix': u'',
 u'network_locale': u'United States',
 u'premium_access_prefix': u'',
 u'pstn_access_prefix': u'9',
 u'service_access_prefix': u''},
. . . . . . . . . 1
```

Selected fields in Countries model.

```
{# data.Countries.country_name, iso_country_code #}

[{u'country_name': u'Australia',
    u'iso_country_code': u'AUS'},
    {u'country_name': u'Bahrain',
    u'iso_country_code': u'BHR'},
    {u'country_name': u'Canada',
    u'iso_country_code': u'CAN'},
    {u'country_name': u'Denmark',
    u'iso_country_code': u'DNK'},
    ...
    {u'country_name': u'United States of America',
        u'iso_country_code': u'USA'}
]
```

Specifying one field in the list will return only a list of values and not a key-value pair list.

```
{ # data.Countries.country_name #}

(continues on next page)
```

```
[u'Australia',
  u'Bahrain',
  u'Canada',
  ...
  ...
  u'United States of America']
```

Device types: a list of all line patterns in the null partition.

```
{# device.cucm.Line.pattern,routePartitionName | routePartitionName:'NullPartition'#}
[{u'pattern': u'55554444',
 u'routePartitionName': u'NullPartition'},
{u'pattern': u'8100240105',
 u'routePartitionName': u'NullPartition'},
 {u'pattern': u'5544332211',
 u'routePartitionName': u'NullPartition'},
 {u'pattern': u'55667722',
 u'routePartitionName': u'NullPartition'},
 {u'pattern': u'8765653',
 u'routePartitionName': u'NullPartition'},
 {u'pattern': u'66776767',
 u'routePartitionName': u'NullPartition'},
{u'pattern': u'3009',
 u'routePartitionName': u'NullPartition'},
 {u'pattern': u'656574747',
 u'routePartitionName': u'NullPartition'},
 . . .
```

Nested structures.

```
{ # device.cucm.Css.* | name: 'PSTN-CSS-Cape-Town'#}
[{u'clause': u'PHONES-PT-Cape-Town:PSTN-PT-Cape-Town:
               Pickup-PT-Cape-Town: CallPark-PT-Cape-Town',
 u'hierarchy': u'5171010ecc2e19483c11291b',
 u'members': {u'member': [{u'index': 1,
                            u'routePartitionName': u'PHONES-PT-Cape-Town',
                            u'uuid': u'{7AF255DC-3A05-A1B4-9E5E-95CD48C3C95F}'},
                           {u'index': 2,
                            u'routePartitionName': u'PSTN-PT-Cape-Town',
                            u'uuid': u'{5FA76732-0074-108A-3A91-23D7C6CAC2E1}'},
                           {u'index': 3,
                            u'routePartitionName': u'Pickup-PT-Cape-Town',
                            u'uuid': u'{F789964F-C95D-4095-F6C7-48E587CBFAD8}'},
                           {u'index': 4,
                            u'routePartitionName': u'CallPark-PT-Cape-Town',
                            u'uuid': u'{B4817113-0F32-6E7F-67B2-20645CFC4509}'}]},
  u'name': u'PSTN-CSS-Cape-Town',
  u'partitionUsage': u'General',
  u'uuid': u'{E678A23E-866A-7CE8-AD0F-8AF138E10A18}'}]
```

```
{# device.cucm.Css.name, members | name: 'PSTN-CSS-Cape-Town'#}

[{u'members': {u'member': [{u'index': 1,
```

(continues on next page)

```
{# device.cucm.Css.name, members.member.2.routePartitionName | name:
    'PSTN-CSS-Cape-Town'#}

[{u'members.member.2.routePartitionName': u'Pickup-PT-Cape-Town',
    u'name': u'PSTN-CSS-Cape-Town'}]
```

9.4.3. Macro- and Macro Function Nesting

Macros and macro functions can be used as arguments of macros and macro functions. Consider the examples below:

- 1. Define a macro Masklen as {{fn.length This is a valid string}}.
- 2. Define a macro as {{fn.mask X macro.Masklen 0}}.
- 3. The result is evaluated as 'XXX...' to the length of 'This is a valid string'.

9.4.4. Conditional Logic Macro Function

Conditional logic in macros is supported by the fn.conditional_logic function that takes two parameters:

- the name of an instance of the data/ConditionalLogic data model
- a value that serves as input to data/ConditionalLogic the data model.

The namespaces that can be used as <code>left_expression</code> values in the data model can depend on the reference to the data model in a Provisioning Workflow. The namespaces - that can also be referenced in full - include:

```
{{self}}{{previous}}{{input}}{{cft}}{{pwf}}
```

Consider the following example data/ConditionalLogic data model called "Is_SLC_Allowed":

```
"conditions": [
   {
       "unary_operator": "NOT",
       "right_expression": "{{ logic.DATA }}",
       "conditional_operator": "AND",
       "condition": "contains",
       "left_expression": "{{ pwf.SLCS }}"
   },
       "unary_operator": "NOT",
       "right_expression": "{{ input.CURRENT_SLC }}",
       "conditional_operator": "AND",
       "condition": "containsStartOf",
       "left_expression": "{{ logic.DATA }}"
   },
       "right_expression": "{{ input.CURRENT_SLC }}",
       "condition": "containsStartsWith",
       "unary_operator": "NOT",
       "left_expression": "{{ logic.DATA }}"
   }
```

Also suppose the Provisioning Workflow for this example has a list variable SLCS and receives an input. CURRENT_SLC value.

Furthermore, during the call of the fn.conditional_logic function in the Provisioning Workflow, it receives a *scalar* value as an argument, for example:

```
{{ fn.conditional_logic Is_SLC_Allowed,128 }
```

- The scalar value reference { { logic.DATA } } can be ommitted from either left_expression or right_expression. Its reference is then assumed.
- The input value is referenced as { { input.CURRENT_SLC } }
- The list that is the Provisioning Workflow variable, is {{ pwf.SLCS }}

As another example, consider a data/ConditionalLogic model called "TestData" with three conditions:

The following function checks if a received input value "AAAaaaBBBaaaCCc" fulfills the condition: contains "AAA" OR "BBB" AND NOT "CCC", as in the macro test using a scalar value:

```
{{ fn.conditional_logic TestData, AAaaaBBBaaaCCc }}
```

The condition resolves to true.

Finally in the following example, the conditional function is used as a condition in a Provisioning Workflow. The Data Model instance of data/ConditionalLogic called "Does Newland Exist" tests a single string matching condition:

The Provisioning Workflow step to apply a Configuration Template if the condition is false. So the step is carried out only if there is not already a country_name called "Newland".

(continues on next page)

9.4.5. Create a Macro In-line

To create a macro in-line, enter the macro directly in:

- 1. Default value in a Data Model.
- 2. Default value in a Configuration Template.
- 3. Condition of an Operation in a Provisioning Workflow.

9.4.6. Create a Macro for Re-use

To create a macro for re-use:

- 1. Choose the hierarchy to which the macro will apply.
- 2. Choose data/Macro.
- 3. Click Add.
- 4. Enter a Name for the macro.
- 5. Enter the macro in the Macro input box.
- 6. Click Save to save the macro.
- 7. The Macro is available for editing from data/Macro/{macro name}, and for use in for example a Configuration Template with a macro reference of the form {{macro.macro name}}.

To call a macro created for re-use:

Macros that have been created and saved can be called using macro syntax but with the namespace "macro" followed by the macro name: "{{macro.macroname}}".

9.4.7. Create a Value Substitution Macro

To write a value substitution macro:

- 1. Determine where to enter the macro: in-line or for re-use.
- 2. Determine the reference of the value to resolve:
- 3. Data Model reference syntax is "data/datamodel.attribute" or "datamodel.attribute". The first instance of the datamodel.attribute will be the target.

4. Enter any static text that should combine with the evaluated macro - if required. Static text is entered outside the "{{" and "}}".

9.4.8. Substitution Macro Examples

```
{{CallManager.host}}
http://{{CallManager.host}}
http://{{CallManager.host}}/{{CallManager.username}}
```

9.4.9. Create an Evaluation Macro

To write an evaluation macro:

- 1. Identify tests and result values:
- 2. A simple test resolves to True or False.
- 3. an If-Then-Else test resolves to a value.
- 4. For a simple test, identify the values and operator to resolve to True or False.
- 5. For an If-Then-Else test, identify If-, Else- and default conditions and values.

9.4.10. Evaluation Macro Examples

```
((DATA1.d1 == y))
```

Explanation: this macro evaluates to true or false if DATA1.d1 is equal to y.

```
((EVALUATE1.val == y)) <{{CallManager.host}}-Enabled>
((EVALUATE1.val == n)) <{{CallManager.host}}-Disabled>
<{{CallManager.host}}-Not set>
```

Explanation: this macro evaluates data model called "EVALUATE1" with attribute "val" - to value of data model called "CallManager" and with attribute "host":

- Appended with "-Enabled" if EVALUATE1.val is y
- Appended with "-Disabled" if EVALUATE1.val is n
- Otherwise appended with "-Not set"

9.4.11. Macro Evaluator

The Macro Evaluator is available to test a macro at a hierarchy level. Refer to the macro functions, syntax and examples in the documentation.

- 1. Choose **Administration Tools > Macro Evaluator** to open the Macro Evaluator input form.
- 2. Enter the macro text in the Macro input box. By default, a macro {# data.Countries.* #} is entered as a test macro to evaluate.
- 3. From the drop-down list, choose the Context Hierarchy at which the macro is to be evaluated.
- 4. Enable and provide values for Context Data if required. Refer to the examples and Desginer Guide for macro reference topics.
- 5. Click Evaluate to run the query.

The result of the evaluated macro is displayed in the Output box.

Index

M	147
Macro Function	<pre>fn.get_endpoint_name, 149</pre>
fn.get_dn_number, 170	<pre>fn.get_hierarchy_phone_statuses, 171</pre>
Macro function	<pre>fn.get_least_used_site_devicepool,</pre>
fn.add, 124	152
fn.add_x_days_to_startdate, 160	fn.get_lines, 166
fn.as_bool, 178	fn.get_phone_status, 23, 170
fn.as_int, 178	fn.get_phone_statuses, 171
fn.as_list, 136, 178	<pre>fn.get_sccp_endpoint_name, 150</pre>
fn.as_string, 178	fn.get_tvpair_list,139
fn.bkey_to_pkid, 178	<pre>fn.get_webex_teams_device_activation_code,</pre>
fn.compare_timestamps, 161	155
fn.contains, 126	<pre>fn.get_webex_teams_user_csv_data_all_users,</pre>
fn.containsIgnoreCase, 127	154
fn.containsStartOf, 127	<pre>fn.get_webex_teams_user_csv_data_specific_user,</pre>
fn.containsStartsWith, 127	154
<pre>fn.cucm_get_line_details, 147</pre>	fn.getMajorMinorVersion, 178
<pre>fn.default_device, 150</pre>	fn.group_by_larger_than_count, 129
<pre>fn.device_meta, 151</pre>	fn.hex_to_int, 178
fn.divide, 125	fn.hierarchy, 164
fn.drop, 156	<pre>fn.hierarchy_friendly_parent_path,</pre>
<pre>fn.drop_from_payload, 157</pre>	164
<pre>fn.email_html, 183</pre>	fn.hierarchy_friendly_path, 164
fn.evaluate, 146	fn.hierarchy_parent, 164
fn.exists, 157	fn.hierarchy_parent_path, 164
fn.false, 155	fn.hierarchy_path, 164
fn.filter_by_rule, 144	fn.index, 125
<pre>fn.filter_roles_by_user_access_profile,</pre>	<pre>fn.instances_match_model_filter_criteria, 141</pre>
146	
fn.fix_non_ascii, 128	fn.int_to_hex, 178 fn.is_int, 124
fn.fix_username, 129	fn.is_list, 130
fn.flatten_list_of_lists, 137	fn.is_none_or_empty, 156
fn.flatten_nested_lists, 138	fn.is_object, 177
fn.force_null, 156	fn.is_site, 164
fn.friendly_path_choices, 164	fn.is_string, 125
fn.from_business_key_format, 178	fn.isexactly, 128
<pre>fn.generate_filters, 142 fn.generic_device_model_custom_operatio</pre>	fn.jabber device name. 153
in.generic_device_modei_custom_operatio	in.join, 126
<pre>fn.get_admin_roles_allowed_at_hn, 145</pre>	<pre>fn.length, 125 fn.lines_from_hierarchy_devices, 150</pre>
<pre>fn.get_cucm_bkeys_associated_via_ndl,</pre>	<pre>fn.list_append, 131 fn.list_contain, 131</pre>
fn.get_cucms_associated_via_ndlr,	fn.list_count, 130

<pre>fn.list_count_item, 131</pre>	fn.request_get, 181
fn.list_empty, 136	fn.request_user_email, 166
fn.list_extend, 134	fn.request_user_name, 166
fn.list_extend_no_dup, 134	fn.request_user_pkid, 166
fn.list_filter_fields, 137	fn.request_user_role, 166
fn.list_in, 131	fn.save_hierarchy_phone_statuses,
fn.list_index, 130	173
fn.list_index_item, 130	fn.seconds_to_text, 160
fn.list_insert, 132	fn.send_webex_teams_message, 154
fn.list_insert_no_dup, 132	fn.send_webex_teams_message_email_group
fn.list_installed_languages, 174	154
<pre>fn.list_installed_languages_admin,</pre>	fn.sequence, 134
	fn.split, 125
<pre>fn.list_installed_languages_by_role,</pre>	fn.sub_string, 126
174	fn.subtract, 124
<pre>fn.list_installed_languages_selfservice,</pre>	
174	fn.true, 155
fn.list_items_to_int, 179	fn.txn_log, 175
fn.list_items_to_string, 178	fn.unset, 155
fn.list_pop, 132	fn.upper, 126
fn.list_remove, 132	fn.validate_name, 128
fn.list_remove_dup, 133	<pre>fn.write_temporary_local_file, 183</pre>
<pre>fn.list_remove_dup_dict, 133</pre>	fn.zero, 155
<pre>fn.list_remove_nulls, 133</pre>	fn.zeropad, 124
fn.list_reverse, 134 Mac	eros (<i>Feature</i>)
<pre>fn.list_set_intersect, 136</pre>	Call Pickup Groups Site Defaults, 96
fn.list_set_left, 136	Hot Dial PLAR Site Defaults, 96
<pre>fn.list_set_right, 137</pre>	Hunt Groups Site Defaults, 96
fn.list_set_symdiff, 135	Lines Site Defaults, 90
fn.list_set_union, 136	Named Macros - Site Defaults Line,
fn.list_sort, 135	106
fn.list_to_string, 178	Named Macros - Site Defaults CUC,
fn.localize, 174	108
fn.localize_choices, 174	Named Macros - Site Defaults
fn.log, 175	Device, 104
fn.lower, 126	Named Macros - Site Defaults
fn.mask, 125	General, 104
fn.match_model_filter_criteria, 140	Named Macros - Site Defaults
fn.maxval, 124	Hotdial, 109
fn.minval, 124	Named Macros - Site Defaults User,
fn.modulo_list, 138	108
fn.multiply, 125	Named Macros Available to
± ± ·	
fn.now, 158	Administrators, 103
fn.now_in_tz, 159	Named Macros in Configuration
fn.null, 156	Templates, 109
fn.object_empty, 177	Named Macros Overview, 81
fn.object_keys, 177	Phones Site Defaults, 92
fn.object_update, 177	Quick Subscriber Site Defaults, 94
fn.one, 135	Subscriber Site Defaults, 93
fn.perform_http_get, 182	Voicemail Site Defaults, 95
fn.pkid_to_bkey, 178	Webex Site Defaults, 96
fn.process_subscriber_line_data, 155	
fn.regex_match, 127	
fn.replace, 128	