



VOSS Insights Dashboard and Arbitrator Maintenance and Upgrade Guide

Release 25.1

March 26, 2025

Legal Information

- Copyright © 2025 VisionOSS Limited.
All rights reserved.
- This information is confidential. If received in error, it must be returned to VisionOSS ("VOSS"). Copyright in all documents originated by VOSS rests in VOSS. No portion may be reproduced by any process without prior written permission. VOSS does not guarantee that this document is technically correct or complete. VOSS accepts no liability for any loss (however caused) sustained as a result of any error or omission in the document.

DOCUMENT ID: 20250326132510

Contents

1	Upgrade and Maintenance	1
1.1	Pre Checks	1
1.2	Backup VM Before Upgrade	1
1.3	Backup Dashboards Before Upgrade	1
1.4	Backup Arbitrator Before Upgrade	2
1.5	Upgrade	6
1.6	Patch Install Steps	11
1.7	Post Checks	12
1.8	DS9 Database Password Management	13
2	Add or Update Certificates	17
2.1	Add Certificates	17
2.2	Update Certificates	18

1. Upgrade and Maintenance

This topic covers the upgrade of Dashboard, Arbitrator and DS-9, as well as maintenance tasks such as [DS9 Database Password Management](#).

1.1. Pre Checks

1. Verify your access to the UI, then verify the application version via the profile menu (your username), for example, **admin** (top right).
2. Verify available storage of the disk of the server, via system/stats dashboards.

1.2. Backup VM Before Upgrade

If the application is a Virtual Machine (VM), then a pre-upgrade snapshot is recommended.


1.3. Backup Dashboards Before Upgrade

This procedure backs up dashboards before you start the upgrade.


1. Log in to the Dashboard user interface as admin (superuser).
2. Click on the **System Configuration** icon (Cog), then select **Import/Export Wizard**.
3. On the **Export** tab, select all the dashboards.
4. Select all the dashboards.
5. Click the **Export .ixtr** button on the top right.
6. Click **Download**.
7. Save the file to your local computer or to a secure network location.

1.4. Backup Arbitrator Before Upgrade

1. Log in to the Arbitrator user interface as admin.
2. Click on the **System Configuration** icon (Cog), then select **Import/Export**.
3. Drag the following items from the **Configuration Items** pane to the **Export** pane:
 - Asset Entries
 - Asset Groups
 - Controls
 - Policy Modules
 - Probe Groups
 - Response Procedures




4. Click **Export**
5. Click **Download**, then save to your local computer or a secure network location.




1.4.1. Admin Menu Backup (Arbitrator or Dashboard)


1. Log in to server using *Putty* via the admin account.
2. Go to the **Administration** menu (either Arbitrator or Dashboard):
 - Arbitrator




- Dashboard



3. Select **Backup Restore**, and then choose **Create a backup**.

**Note:**

- This backup creates a backup tar.bz2 file in the lxt_archive/ directory. If required, the **Administration** menu can be used to restore a selected backup.



- Any themes that were present on the system are also backed up and will also be available from the restore list.



1.5. Upgrade

1.5.1. Upgrade Timings

Note: The total upgrade time depends on how busy the system is.


Averages:

- Arbitrator = Approx 15-45 Mins
- Dashboard = Approx 20-60 Mins
- DS9 = Approx 20-40 Mins


1.5.2. Upgrade Arbitrator or Dashboard

1. Using *Winscp* and the drop account, copy the file (example file for the arbitrator insights-arbitrator-<from>-<to>.lxs) to the lxt_upgrade directory.


Note: The drop account username is “drop”. You can set the password via the **Administration** menu.



2. Log in to the server using *Putty* via the Admin account.
3. From the **Administration** menu, select **Upgrade**.



4. On **VOSS Upgrade**, select **Check and Upgrade**, click **OK**.



1.5.3. Upgrade DS9


This procedure upgrades DS9.

Pre-requisites:


- Using *Winscp* and the drop account, copy the *.lisp file to be used for the upgrade into the drop account's *lxt_upgrade* sub-directory.

Note:

- The naming convention for Insights upgrade files means that the system is able to detect the file to use for the upgrade. For Insights products, *.lisp file is copied into the drop account's *lxt_upgrade* sub-directory, and the system fetches the file from that location.
- The drop account username is "drop". You can set the password via the **Administration** menu.




1. Connect to the DS9 server using an SSH client on port 22 and login using the admin credentials to access the **Administration** menu.



2. Select **System > Software Upgrade**.




3. Select **Check and Upgrade**.




1.6. Patch Install Steps

1. Using *Winscp* and the drop account, copy the file (example file for the arbitrator insights-arbitrator-<from>-<to>.lxs) to the lxt_upgrade directory.
2. Log on to the server using *Putty* and the admin user credentials
3. From the **Administration** menu, select **Upgrade**



4. Select **Check and Upgrade**:




(Optional) Select **Perform Checksum** and enter the downloaded filename. This step will verify the downloaded file against its .sha256 file.

5. Once the upgrade completes, reboot the server then log in again to verify.

1.7. Post Checks

Verify that the version of your system is updated. To do this via the GUI, click the **System Configuration** icon (Cog), then select **About**.



Note: If the version does not appear to be updated, clear your browser's cache and reconnect.


1.8. DS9 Database Password Management

DS9 is installed with a default, hidden password and Dashboard user `lpublic`.

This database password can however be modified, as indicated below.

1.8.1. Maintain DS9 Database Password on DS9


1. On the DS9 server, log in as `admin` from the console and from the **Administration** menu, select **Change Passwords**.
2. Select **Change DS9 Public Database Password** and modify the password. (Note: only alphanumeric characters are allowed)



3. Verify the credential configuration on the Arbitrator - see below.
4. Update the Dashboard **Data Sources** password for the DS9 server - see below.

1.8.2. Maintain DS9 Database Password on Arbitrator

1. Log in as admin from the console and from the **Administration** menu, select **Change Passwords**.
2. Select **Change DS9 Public Database Password**.



3. Enter the DS9 IP address on the console and modify the password. (Note: only alphanumeric characters are allowed)

A change from the default credentials will also reflect on the Arbitrator menu: **CREDENTIAL CONFIGURATION**.

<input type="checkbox"/> Name	Username	Password	Confirm	
<input type="checkbox"/> ccmadmin	*****	*****	*****	
<input type="checkbox"/> vossaxl	*****	*****	*****	
<input type="checkbox"/> admin	*****	*****	*****	
<input type="checkbox"/> insights-axl	*****	*****	*****	
<input type="checkbox"/> snmp	*****	*****	*****	
<input type="checkbox"/> voss	*****	*****	*****	
<input type="checkbox"/> 10.13.37.51_ds9_database_password	*****	*****	*****	

If this entry is removed, the DS9 credentials revert to the default, hidden credentials. While this entry can also be modified, it is advised to carry out the task from the console **Change DS9 Public Database Password** menu.

1.8.3. Maintain DS9 Database Password on Dashboard

When a DS9 server password is modified on DS9 or the Arbitrator as indicated above, the modified password needs to be updated on Dashboard the **Data Sources** entry.

1. From the **System Configuration** icon on the dashboard, select **Data Sources**.
2. Update the **Password** field for all **Data Sources** that match the related DS9 host.

Data Sources

DS9 SNMP Postgres Database - 10.13.37.52

New Data Source

Name

DS9 SNMP Postgres Database - 10.13.37.52

Data Source Type

DS9 SNMP Postgres Database

Host

10.13.37.52

Port

5432

Username

ixpublic

Password


.....

Delete

Save

2. Add or Update Certificates

Users can now update SSL Certificates and SSL keys from the Admin console menu.




2.1. Add Certificates

To add your own certificate, you will need both the certificate and private key.

1. SSH to the system using admin account
2. Select **Network Configuration**
3. Select **Apache Certs**
4. Select **Insert Cert**
5. Paste in customer certificate

A certificate has the following header and footer

```
--BEGIN CERTIFICATE--  
--END CERTIFICATE--
```



6. Select **Insert Private Key**

7. Paste in customer private key

A private key has the following header and footer

```
--BEGIN PRIVATE KEY--
--END PRIVATE KEY--
```



8. Select **Display Cert Details** to view certificate details.

9. Select **Back** and exit the menu.

10. Refresh the browser. The system should be using the new certificate.

2.2. Update Certificates

If you want to generate a new unsigned certificate or to reset a certificate and private key:

1. SSH to the system using admin account
2. Select **Network Configuration**
3. Select **Apache Certs**
4. Select **Generate New Unsigned Cert**

5. When prompted, fill in the information requested.

```
Generating a 2048 bit RSA private key
.....
.....+++
writing new private key to '/etc/apache2/server.key'
-----
You are about to be asked to enter information that will be incorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
-----
Country Name (2 letter code) [AU]:
```

6. Select **Back** and exit the menu.
7. Refresh browser. The system should be using the new unsigned certificate.